

Category: IT Operations & Infrastructure (Internal)

Document ID: doc_17_printer_setup

Effective Date: January 1, 2026

Revision: 1.8

VoltVibe Office IT Infrastructure: Local Printer Setup & Network Guide

1. IT Infrastructure and Printer Deployment

This internal IT setup guide details the network configuration, security credentials, and troubleshooting protocols for local printing hardware at VoltVibe corporate office spaces. Maintaining print queue security is critical to prevent the exposure of proprietary design schematics, financial disclosures, and internal personnel records. VoltVibe utilizes LaserJet Enterprise M507 printers on all office floors.

2. Network Settings & IP Configurations

All office printers are assigned static IP addresses inside the dedicated office subnet to prevent DHCP lease renewal conflicts. The standard network settings are defined in the table below:

Parameter Name	Default Subnet Setting	Administrative Protocol Details
Subnet IP Pool	10.150.40.10 to 10.150.40.50	Static allocations reserved for printing hardware.
Subnet Mask	255.255.255.0	Standard Class C private subnet mask.
Default Gateway	10.150.40.1	Core Cisco access switch gateway IP.
DNS Server Primary	10.100.10.10	VoltVibe internal Domain Controller DNS.
Secure Port	Port 9100 / Raw IP	Standard TCP RAW port with TLS 1.3 encryption forced.

3. Secure Printing via FollowMe Badge Release

To prevent confidential materials from sitting unattended in exit trays, secure badge-release printing is enabled across all units. Under this system, when an employee prints a document, the job is held encrypted on the central FollowMe print server. The employee must walk to any physical printer, tap their NFC corporate access badge on the reader terminal, and select their print job to release it. Jobs remaining in the server queue for more than 4 hours are automatically purged to conserve memory resources.

3.1 Troubleshooting and Maintenance Procedures

In the event of a paper jam, the printer screen will display a diagnostic code and guide the operator through clearing the path. Only IT helpdesk technicians are authorized to open the logical board casing or replace the fuser module. Toner cartridge replacements must be logged in the IT inventory spreadsheet to maintain supply audits.

3.2 The Secure Air-Gapped Printing Mandate

CRITICAL SECURITY EXCLUSION: Under no circumstances should documents containing proprietary battery schematics, customer credit card details, or Class 9 Dangerous Goods freight manifests (as outlined in doc_23_warehouse_safety_protocol.pdf) be sent to the standard network print queue. These files must be printed strictly on the dedicated, air-gapped secure printer located inside the Bay 2 engineering office (Asset ID: IT-SEC-PRT-02). This printer is completely disconnected from the corporate Wi-Fi network and requires a direct local USB connection from a secure laptop, ensuring zero exposure to external network vectors.