
# **TD1.3**


Annexe 1 :	
Annexe 3:	
Δημογο 4 ·	





## Annexe 1:






### routeur:

```
RI#configure t
Enter configuration commands, one per line. End with CNTL/Z.
RI(config)#interface FastEthernet 0/1
RI(config:if)#ip address 192.168.1.254
% Incomplete command.

RI(config-if)#ip address 192.168.1.254 255.255.255.0
RI(config-if)#no shutdown
RI(config-if)#exit
RI(config)#
*Mar 1 00:08:51.263: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to up
*Mar 1 00:08:52.263: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
RI(config)#interface FastEthernet0/0
RI(config)#interface FastEthernet0/0
RI(config:if)#no shutdown
RI(config:if)#no shutdown
RI(config:if)#no shutdown
RI(config)#
*Mar 1 00:09:36.795: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Mar 1 00:09:37.795: %LINK-3-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
*Mar 1 00:09:37.795: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
*Mar 1 00:09:37.795: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
*Mar 1 00:09:37.795: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
*Mar 1 00:09:37.795: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

### Annexe 3:



```
R1#enable
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip name-server 8.8.8.8
R1(config)#end
Enter configuration commands, one per line. End with CNTL/Z. R1(config)#interface FastEthernet0/0
R1(config-if)#no shutdown
"Mar 1 00:04:34.567: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
"Mar 1 00:04:35.567: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
R1(config-if)#end
R1#
*Mar 1 00:04:56.9
R1#
      1 00:04:56.915: %SYS-5-CONFIG_I: Configured from console by console
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 10.10.2.1 255.255.255.0
R1(config-if)#exit
R1(config)#exit
R1#
      1 00:09:46.719: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEthernet0/1
R1(config-if)#no shutdown
R1(config-if)#end
*Mar 1 00:06:03.775: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to up
*Mar 1 00:06:04.883: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
R1(config-if)#end
    1 00:06:07.811: %SYS-5-CONFIG_I: Configured from console by console
R1#show ip interface brief
                                   IP-Address
                                                       OK? Method Status
Interface
                                                                                                   Protocol
FastEthernet0/0
                                   unassigned
                                                                                                   up
                                 unassigned
FastEthernet0/1
                                                       YES unset up
                                                                                                   up
FastEthernet1/0
                                 unassigned
                                                       YES unset administratively down down
FastEthernet2/0
                                                       YES unset administratively down down
                                 unassigned
                                                       YES unset administratively down down
FastEthernet3/0
                                 unassigned
                                                       YES unset administratively down down
FastEthernet4/0
                                 unassigned
FastEthernet5/0
                                                       YES unset administratively down down
                                  unassigned
                                                       YES unset administratively down down
FastEthernet6/0
                                  unassigned
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#no ip domain lookup
R1(config)#end
 R1#
```

1 00:24:56.155: %SYS-5-CONFIG\_I: Configured from console by console

'Mar

#### Annexe 4:

```
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp excluded-address 10.10.2.1
R1(config)#ip dhcp excluded address 10.10.2.2
R1(config)#ip dhcp pool mypool
R1(dhcp-config)#network 10.10.2.0 255.255.255.0
R1(dhcp-config)#default-router 10.10.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#exit
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 10.10.2.1 255.255.255.0
R1(config-if)#ip helper-address 10.10.2.1
R1(config-if)#end
 R1#
 *Mar 1 00:37:32.275: %SYS-5-CONFIG_I: Configured from console by console
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address dhcp
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#end
R1#
 *Mar 1 00:41:49.575: %SYS-5-CONFIG_I: Configured from console by console
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z. R1(config)#interface FastEthernet 0/0
R1(config-if)#ip nat outside
*Mar 1 01:04:05.759: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVIO, changed state to up
R1(config-if)#interface FastEthernet 0/1
R1(config-if)#ip nat inside
R1(config-if)#ip nat inside source list 1 interface FastEthernet 0/0 overload
R1(config)#access-list 1 permit 10.10.2.1 255.255.255
 6 Incomplete command.
R1(config)#access-list 1 permit 10.10.2.1 255.255.255.0
R1(config)#end
R1#wr
 *Mar 1 01:06:48.411: %SYS-5-CONFIG_I: Configured from console by console
 R1#write memory
Building configuration...
```