

*****RHEL 8 KERNEL UPDATE*****

1] Go to the rhel 8 machine

2] Open the terminal and type the command:- `uname -r`

```
[root@localhost ~]# uname -r
4.18.0-348.el8.x86_64
```

3] Go to the brauser and search (letaust version of rhel 8)

4] download the letest version of rhel 8 in window

Download


Package - kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm

SHA-256: d8df6855a1ae0e3ee58c6e5830f77c2b97b016248dc0dc52825564c46c9cfb6a

Download Now

43.4 MB

5] Open the winscp and trasfer the flel to rhel 8 (/opt/)



6] Open the rhel 8 machine

7] Go to /opt directory and run the coomad ; - `ls`

```
[root@localhost opt]# ls
kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm
[root@localhost opt]#
```

8) Run this command :-

```
[root@localhost opt]# rpm -Fvh kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm
warning: kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm: Header V4 RSA/SHA256 Signature, key ID fd4
31d51: NOKEY
error: Failed dependencies:
    kernel-core-uname-r = 4.18.0-348.el8.x86_64 is needed by (installed) kernel-4.18.0-348.el
8.x86_64
    kernel-uname-r = 4.18.0-348.el8.x86_64 is needed by (installed) kernel-modules-4.18.0-348
.el8.x86_64
[root@localhost opt]# rpm -ivh kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm
warning: kernel-core-4.18.0-553.8.1.el8_10.x86_64.rpm: Header V4 RSA/SHA256 Signature, key ID fd4
31d51: NOKEY
Verifying... ##### [100%]
Preparing... ##### [100%]
Updating / installing...
 1:kernel-core-4.18.0-553.8.1.el8_10##### [100%]
[root@localhost opt]#
```

10) Reboot the system

11) Open the terminal and run this command :- `uname -r`

```
[root@localhost Desktop]# uname -r
4.18.0-553.8.1.el8_10.x86_64
```

12) updated successfully