

IPsec Tunnel

VPN Creation Wizard

1 VPN Setup

2 Authentication

3 Policy & Routing

4 Review Settings

Name

Site1-Site2.

Template type

Site to Site

Hub-and-Spoke

Remote Access

Custom

NAT configuration

No NAT between sites

This site is behind NAT

The remote site is behind NAT

Remote device type

FortiGate

Cisco

VPN Creation Wizard

✓ VPN Setup

2 Authentication

3 Policy & Routing

4 Review Settings

Remote device

IP Address

Dynamic DNS

Remote IP address

1.1.1.2

Outgoing Interface

wan2

Authentication method

Pre-shared Key

Signature

Pre-shared key

•••••

VPN Creation Wizard

✓ VPN Setup

✓ Authentication

3 Policy & Routing

4 Review Settings

Local interface

internal2

×

+

Local subnets

192.168.10.0/24

+

Remote Subnets

192.168.20.0/24

+

Internet Access

i

None

Share Local

Use Remote

VPN Creation Wizard

✓ VPN Setup

✓ Authentication

✓ Policy & Routing

4 Review Settings

i

The following settings should be reviewed prior to creating the VPN.

Object Summary

Phase 1 interface

Site1-Site2.

Local address group

Site1-Site2._local

Remote address group

Site1-Site2._remote

Phase 2 interface

Site1-Site2.

Static route

static

Blackhole route

static

Local to remote policies

vpn_Site1-Site2._local

Remote to local policies

vpn_Site1-Site2._remote

From Site1-Site2

Q > ? 🔔 👤 user			
+ Create New Edit Delete Show Matching Logs Search Q			
Tunnel	Interface Binding	Status	Ref.
Site to Site - FortiGate 1			
Site1-Site2	wan2	Up	4

From Site2-Site1

FortiGate-60E Dashboard Network Policy & Objects Security Profiles VPN Overlay Controller VPN IPsec Tunnels IPsec Wizard IPsec Tunnel Template SSL-VPN Portals SSL-VPN Settings	Q > ? 🔔 1 👤 user			
	+ Create New Edit Delete Search Q			
	Tunnel	Interface Binding	Status	Ref.
	Site to Site - FortiGate 1			
	Site2-Site1	wan2	Up	4

SSL VPN

Connection Settings ⓘ

Enable SSL-VPN ☒

Listen on Interface(s)

 wan1 ✕

+

Listen on Port

8080



Web mode access will be listening at <https://192.168.64.17:8080>

Server Certificate

 SSL-VPN ▼

Redirect HTTP to SSL-VPN ☐

Restrict Access

Allow access from any host

Limit access to specific hosts

Negate Source

☐

Idle Logout

☒

Inactive For

300

Seconds

Require Client Certificate ☐

Tunnel Mode Client Settings ⓘ

Address Range

Automatically assign addresses

Specify custom IP ranges

Tunnel users will receive IPs in the range of 10.212.134.200 - 10.212.134.210

DNS Server

Same as client system DNS

Specify

Specify WINS Servers ☐

Web Mode Settings

Language ⓘ **Browser preference** System

Authentication/Portal Mapping ⓘ

+ Create New ✎ Edit 🗑 Delete ✉ Send SSL-VPN Configuration	
Users/Groups ⚙	Portal ⚙
 VpnUser	full-access
All Other Users/Groups	web-access
2	

FortiGate-60E

Dashboard

Network

Policy & Objects

Firewall Policy

Local In Policy

IPv4 DoS Policy

Addresses

Internet Service Database

Services

Schedules

≡ 🔍

Edit Address

Name

SSL_VPN_Pool

Color

 Change

Type

IP Range

IP Range



10.8.0.10-10.8.0.50

Interface

☐ any

Comments

Write a comment... 0/255



Policies

Name	Source	Destination	Schedule	Service	Action	NAT	Security Profiles	Log
Internal → wan1 1								
	all	all	always	ALL	ACCEPT	Enabled	SSL no-inspection	UTM
Internal2 → Site1-Site2 1								
vpn_Site1-Site2_local_0	Site1-Site2_local	Site1-Site2_remote	always	ALL	ACCEPT	Disabled	SSL no-inspection	UTM
Internal3 → dmz 2								
Outside-DMZ	all	outsideToDMZ	always	HTTP	ACCEPT	Enabled	SSL no-inspection	UTM
SSH	all	Kali	always	SSH	ACCEPT	Enabled	SSL no-inspection	UTM
Site1-Site2 → Internal2 1								
vpn_Site1-Site2_remote_0	Site1-Site2_remote	Site1-Site2_local	always	ALL	ACCEPT	Disabled	SSL no-inspection	UTM
SSL-VPN tunnel interface (ssl.root) → Internal2 1								
VPN-Tunnel	VpnUser all	Site1-Site2_local_subnet_1	always	ALL	ACCEPT	Enabled	SSL no-inspection	UTM
Implicit 1								

Ipv4 DoS policy

ID	Name	Interface	Source Address	Destination Address	Service
1	DoS Project Policy	wan1	all	all	ALL

Name	DoS Project Policy
Incoming Interface	wan1
Source Address	all
Destination Address	all
Service	ALL

L3 Anomalies

Name	Logging	Action	Threshold
ip_src_session	☒	Disable Block Monitor	5000
ip_dst_session	☒	Disable Block Monitor	5000

L4 Anomalies

Name	☒ Logging	Action Disable <input checked="" type="button" value="Block"/> Monitor	Threshold
tcp_syn_flood	☒	Disable <input checked="" type="button" value="Block"/> Monitor	2000
tcp_port_scan	☒	Disable <input checked="" type="button" value="Block"/> Monitor	10
tcp_src_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000
tcp_dst_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000
udp_flood	☒	Disable <input checked="" type="button" value="Block"/> Monitor	2000
udp_scan	☒	Disable <input checked="" type="button" value="Block"/> Monitor	2000
udp_src_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000
udp_dst_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000
icmp_flood	☒	Disable <input checked="" type="button" value="Block"/> Monitor	250
icmp_sweep	☒	Disable <input checked="" type="button" value="Block"/> Monitor	100
icmp_src_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	300
icmp_dst_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	1000
sctp_flood	☒	Disable <input checked="" type="button" value="Block"/> Monitor	2000
sctp_scan	☒	Disable <input checked="" type="button" value="Block"/> Monitor	1000
sctp_src_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000
sctp_dst_session	☒	Disable <input checked="" type="button" value="Block"/> Monitor	5000

Comments 0/1023

Enable this policy ☒

Log Setting

Global SettingsLocal LogsThreat Weight

UUIDs in Traffic Log ?

Address ☐

Log Settings

Event logging

AllCustomize

Local traffic logging

AllCustomize

Syslog logging

☒ Enable☐ Disable

IP address/FQDN

206.206.206.16

GUI Preferences

Resolve hostnames ?

☒

Resolve unknown applications ?

☒

Apply

splunk>enterpriseApps

MessagesSettingsActivityHelpFind

UDP

New Local UDP

Data inputs > UDP

Showing 1-2 of 2 items

filter

25 per page

UDP port	Source type	Status	Actions
444	fortigate_log	Enabled Disable	Clone Delete
555	fortigate_log	Enabled Disable	Clone Delete

Accessing DMZ servers

The image shows a Kali Linux terminal window and a web browser window. The terminal window displays the following commands and output:

```
C:\Windows\System32>
C:\Windows\System32>ssh kali@10.10.10.1 -p 8080
kali@10.10.10.1's password:
Linux kali 6.18.12+kali-amd64 #1 SMP PREEMPT_DYNAMIC Kali 6.18.12-1kali1 (2026-02-25) x86_64

The programs included with the Kali GNU/Linux system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Kali GNU/Linux comes with ABSOLUTELY NO WARRANTY, to the extent
permitted by applicable law.
kali@kali:~$
```

The web browser window shows the Apache2 Debian Default Page. The page has a title "Apache2 Debian Default Page" and a sub-header "debian". It includes a red banner that says "It works!". The main content area contains the following text:

This is the default welcome page used to test the correct operation of the Apache2 server after installation on Debian systems. If you can read this page, it means that the Apache HTTP server installed at this site is working properly. You should **replace this file** (located at `/var/www/html/index.html`) before continuing to operate your HTTP server.

If you are a normal user of this web site and don't know what this page is about, this probably means that the site is currently unavailable due to maintenance. If the problem persists, please contact the site's administrator.

Configuration Overview

Debian's Apache2 default configuration is different from the upstream default configuration, and split into several files optimized for interaction with Debian tools. The configuration system is **fully documented in `/usr/share/doc/apache2/README.Debian.gz`**. Refer to this for the full documentation. Documentation for the web server itself can be found by accessing the **manual** if the `apache2-doc` package was installed on this server.

The configuration layout for an Apache2 web server installation on Debian systems is as follows:

```
/etc/apache2/
|-- apache2.conf
|   |-- ports.conf
|-- mods-enabled
|   |-- *.load
|   |-- *.conf
|-- conf-enabled
|   |-- *.conf
|-- sites-enabled
|   |-- *.conf
```

- `apache2.conf` is the main configuration file. It puts the pieces together by including all remaining configuration files when starting up the web server.
- `ports.conf` is always included from the main configuration file. It is used to determine the listening ports for incoming connections, and this file can be customized anytime.
- Configuration files in the `mods-enabled/`, `conf-enabled/` and `sites-enabled/` directories contain particular configuration snippets which manage modules, global configuration fragments, or virtual host configurations, respectively.
- They are activated by symlinking available configuration files from their respective `*-available/` counterparts. These should be managed by using our helpers `a2enmod`, `a2dismod`, `a2ensite`, `a2dissite`, and `a2enconf`. See their respective man pages for detailed information.
- The binary is called `apache2`. Due to the use of environment variables, in the default configuration, `apache2` needs to be started/stopped with `/etc/init.d/apache2` or `apache2ctl`. **Calling `/usr/bin/apache2` directly will not work** with the default configuration.

At the bottom of the page, there is a link to "Activate Windows" and a message "Go to Settings to activate Windows."

Udp Attack

```
Pentmenu>7
UDP Flood uses hping3 ... checking for hping3 ...
hping3 found, continuing!
Enter target:
192.168.64.17
Enter target port (defaults to 80):
55
Using Port 55
Enter random string (data to send):
ayush
Enter Source IP, or [r]andom or [i]nterface IP (default):
i
Starting UDP Flood. Use 'Ctrl c' to end and return to menu
HPING 192.168.64.17 (eth0 192.168.64.17): udp mode set, 28 headers + 5 data b
ytes
[main] memlockall(): No such file or directory
Warning: can't disable memory paging!
hping in flood mode, no replies will be shown
█
```

Users and Group

Edit User

Username

ayush

User Account Status

↑ Enabled

↓ Disabled

User Type

Local User

Password

●●●●●●●●

User Group

🗄 VpnUser

+

×

☐ Two-factor Authentication

Edit User Group

Name

Type

Members

 ayush

+

×