



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Project

Project Settings

Project Name

واجب 2

Project Location

C:\Users\zero_one\Desktop

Browse

Application Structure

Advanced

☐ Do not generate the main()

Toolchain Folder Location

C:\Users\zero_one\Desktop\واجب 2\

Toolchain / IDE

STM32CubeIDE

☒ Generate Under Root

Code Generator

Linker Settings

Minimum Heap Size

0x200

Minimum Stack Size

0x400

Advanced Settings

Thread-safe Settings

Cortex-M3NS

☐ Enable multi-threaded support

Thread-safe Locking Strategy

Default – Mapping suitable strategy depending on RTOS selection.

Mcu and Firmware Package

Mcu Reference

STM32F103C8Tx

Firmware Package Name and Version

STM32Cube FW_F1 V1.8.5

☒ Use latest available version☒ Use Default Firmware Location

Firmware Relative Path

C:/Users/zero_one/STM32Cube/Repository/STM32Cube_FW_F1_V1.8.5

Browse





Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Categories A-Z

- System Core
- analog
- Drivers
- RTC
- TIM1
- TIM2
- TIM3
- TIM4
- Connectivity
- Computing
- Middleware and Software Packs

TIM3 Mode and Configuration

Mode

- ☒ Internal Clock

Channel1 Disable

Channel2 Disable

Channel3 Disable

Configuration

Reset Configuration

- ☒ NVIC Settings
- ☒ DMA Settings
- ☒ Parameter Settings
- ☒ User Constants


Configure the below parameters :

Search (Ctrl+F)

- Counter Settings
 - Prescaler (PSC - 16 bits ... 7199
 - Counter Mode Up
 - Counter Period (AutoRel... 4999
 - Internal Clock Division (C... No Division
 - auto-reload preload Disable
- Trigger Output (TRGO) Paramet...
 - Master/Slave Mode (MS... Disable (Trigger input effect not del...
 - Trigger Event Selection Reset (UG bit from TIMx_EGR)

Pinout view

System view





Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Categories A->Z

- System Core
- analog
- Drivers
- RTC
- TIM1
- TIM2
- TIM3**
- TIM4
- Connectivity
- Computing
- Middleware and Software Packs

TIM3 Mode and Configuration

Mode

☒ Internal Clock

Channel1

Channel2

Channel3

Configuration


☒ Restore default values for all peripheral parameters

☒ Parameter Settings ☒ User Constants

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



STM32F103C8Tx

واجهة - Clock Configuration.2

GENERATE CODE

Pinout & Configuration

Clock Configuration

Project Manager

Tools

