



ABLESTACK Online Docs
ABLESTACK-V4.0-4.0.15

API 문서

API 문서

개요

ABLESTACK API Docs 메뉴는 Mold의 기능을 프로그래밍적으로 제어할 수 있는 API에 대한 문서를 제공합니다. 이 메뉴에서는 API 엔드포인트, 요청 파라미터, 응답 형식 등을 상세히 설명하며, 개발자가 Mold의 다양한 기능을 자동화하거나 외부 시스템과 통합할 때 필요한 정보를 제공합니다. 각 API 호출에 대한 예제와 응답 형식(JSON, XML 등)도 제공되어 효율적인 사용이 가능합니다.

API 문서 조회

1. ABLESTACK Mold에서 사용 가능한 API 목록을 제공합니다. 목록을 선택하여 API를 요청 및 응답 파라미터를 확인할 수 있습니다.

The screenshot displays the ABLESTACK API Docs interface. On the left, a sidebar lists various system components like '대시보드', '컴퓨트', '스토리지', etc., with 'API 문서' selected at the bottom. The main area shows the 'UpdateVmNicLinkState' API details. It includes a search bar, a list of API endpoints, and a detailed view of the selected API. The detailed view shows the API name, its type (Asynchronous API), and a description. Below this, there are two tables: '요청 파라미터:' (Request Parameters) and '응답 파라미터:' (Response Parameters). The '요청 파라미터:' table lists parameters like 'linkstate', 'nicid', and 'virtualmachineid' with their respective types and descriptions. The '응답 파라미터:' table lists response parameters like 'hostcontrolstate', 'rootdevicetype', 'isodisplaytext', etc., with their types and descriptions.

이름	필수 사항	유형	설명
linkstate	true	boolean	Secondary IP Address
nicid	true	uuid	the ID of the nic to which you want to Link state
virtualmachineid	true	uuid	Virtual Machine ID

이름	유형	설명
hostcontrolstate	string	the control state of the host for the virtual machine
rootdevicetype	string	device type of the root volume
isodisplaytext	string	an alternate display text of the ISO attached to the virtual machine
userdatapolicy	string	the userdata override policy with the userdata provided while deploying VM
project	string	the project name of the vm
displayvm	boolean	an optional field whether to the display the vm to the end user or not.
autoscalevmgroupname	string	Name of AutoScale VM group
guestosid	string	Os type ID of the virtual machine
domainid	string	the ID of the domain in which the virtual machine exists
userdataetails	string	list of variables and values for the variables declared in userdata
name	string	the name of the virtual machine
cpunumber	integer	the number of vCPUs this virtual machine is using
hostid	string	the ID of the host for the virtual machine

ABLESTACK Online Docs