
# Start here: sign in at the base

Open the base address supplied by your station administrator.




### 1 Use your own account

Your administrator creates it.

The pictured name is only an example.

### 2 Sign in

Viewer: read and download.

Operator: manage station records.


## Use the right address

Base: your configured HTTPS address. Development: http://127.0.0.1:5173/

Base screen shown with an illustrative test session; no default account is installed.

# One place for station records

Use the top row to choose the work you need.





## Personnel + vehicles > Plan a mission > Add cargo > Review updates

Inventory: add an item, then adjust stock with a reason. Alerts: acknowledge, then resolve.

Illustrative account and unsaved example form. No live stock was created.

# Know where your files are

Data Management shows the backend folder, not every folder on your computer.




### 1 Folder path

This is the real storage location.
On a base server, files live there.

### 2 Originals / copies

Switch folders to see
the stored versions.


### 3 Add a file

Choose or drop files.
Maximum: 20 MiB per file.

**The remote pane is a placeholder.**
It does not list remote files yet.

# Set a level. Prepare a copy.

Choose Edit data level beside an original file.




**1 Choose the level**

Save data level first.
A label does not encrypt.

**2 Use this file**

Or drag the original
into the preparation area.


**3 Protect the copy**

Compress if useful.
Choose Yes to encrypt.
Enter matching passwords.

**The original stays unchanged and unencrypted. Keep the encryption password safely.**

# Find and restore a copy

Prepared copies are separate files. Creating one does not send it anywhere.







## 1 Download prepared copy

Keeps its compressed / encrypted format.


## 2 Restore and download

Enter its password when encrypted.
Downloads the original contents to your computer.

**Lost password? The application cannot recover it.**

# Check another device

This Connection area is in local / field mode. Base mode shows base storage status.



## Connection

Reachable

Check the other device's backend. These are real network checks; they do not send expedition files.

Other device address

http://127.0.0.1:8010

Automatic checks

Every 30 seconds

Apply and reconnect | Check now | Disconnect

```
Checking: http://127.0.0.1:8010
```

Backend health check passed. File browsing and transfer are not connected yet.
Last response: 14/10/2026, 18:34:27 · Response time: 37 ms · Backend version: 0.3.0

Use localhost or a private network IP. "Reachable" is the last health-check result, not a permanent link or proof of identity. Editing settings does not change a running check until applied. Leaving Data Management or reloading stops checks; the address and interval stay saved.

### 1 Enter the backend address

Use a private-network IP or localhost.
Connect saves the address in this browser.

### 2 Watch the last response

Check now repeats the check.
Apply and reconnect uses changed settings.

### Reachable means a health check succeeded.

It does not mean files were transferred. Leaving the page stops automatic checks.

# How data reaches the base

Illustrated network example - not a screenshot of a deployed connection.

### Field device A

Record events locally.
Keep them while offline.
PMCE retries delivery.

send →

### Network

Private LAN or Internet
Configured HTTPS base
Device credential

receive →

### Base station

Receive and store
Verify delivery
Show received records

← **receipt back to sender**

### Browser connection check

Tests health only.
No remote folder browsing or file sending.

### Device file delivery API

Requires an authorized device credential.
A receipt confirms stored bytes.

For a deployed base, your administrator sets the hostname, HTTPS and device access.

Do not use localhost as another computer's address: it always means that computer itself.

# If something does not work

Keep the original. Read the message. Retry only when you know the result.

## Cannot sign in

Use the administrator-provided account.

Ask the administrator if the account is locked or disabled.

## Storage unavailable

Check that the backend is running, then choose Retry storage.

After an interrupted upload, refresh and look for the file before retrying.

## Other device unreachable

Check its address, server, network and firewall.

Use Check now. Reachability is separate from device authorization.

## Need setup help?

README: install and run | docs/BASE_STATION.md: accounts, HTTPS and backups

This guide shows current behavior. Remote file browsing and the field transfer UI are not implemented.