Códigos más comunes

Trasladarse a una Celda

Range("A1").Select

Escribir en una Celda

Activecell.FormulaR1C1="Paty"

Letra Negrita

Selection.Font.Bold = True

Letra Cursiva

Selection.Font.Italic = True

Letra Subrayada

Selection.Font.Underline = xlUnderlineStyleSingle

Centrar Texto

With Selection
.HorizontalAlignment = xlCenter
End With

Alinear a la izquierda

With Selection
.HorizontalAlignment = xlLeft
End With

Alinear a la Derecha

With Selection
.HorizontalAlignment = xlRight
End With

Tipo de Letra (Fuente)

With Selection.Font
.Name = "AGaramond"
End With

Tamaño de Letra (Tamaño de Fuente)

With Selection.Font .Size = 15 End With

Copiar

Selection.Copy

Pegar

ActiveSheet.Paste

Cortar

Selection.Cut

Ordenar Ascendente

Selection.Sort Key1:=Range("A1"), Order1:=xlAscending, Header:=xlGuess, _ OrderCustom:=1, MatchCase:=False, Orientation:=xlTopToBottom

Orden Descendente

Selection.Sort Key1:=Range("A1"), Order1:=xlDescending, Header:=xlGuess, _ OrderCustom:=1, MatchCase:=False, Orientation:=xlTopToBottom

Buscar

Cells.Find(What:="Paty", After:=ActiveCell, LookIn:=xlFormulas, LookAt _ :=xlPart, SearchOrder:=xlByRows, SearchDirection:=xlNext, MatchCase:= _ False).Activate

Insertar Fila

Selection.EntireRow.Insert

Eliminar Fila

Selection.EntireRow.Delete

Insertar Columna

Selection.EntireColumn.Insert

Eliminar Columna

Selection.EntireColumn.Delete

Abrir un Libro

Workbooks.Open Filename:="C:\Mis documentos\video safe 3.xls"

Grabar un Libro

ActiveWorkbook.SaveAs Filename:="C:\Mis documentos\piscis.xls", FileFormat _ :=xlNormal, Password:="", WriteResPassword:="", ReadOnlyRecommended:= _ False, CreateBackup:=False