






QEMU VM template configuration
PVE
General settings
HDD
CD/DVD
Network
Advanced
Usage
Template name:
PVE
Default name format:
{name}-{0}
Symbol:
proxmox.png
Browse...
Category:
End devices
RAM:
8192 MB
vCPUs:
4
Qemu binary:
/bin/qemu-system-x86_64 (v10.2.1)
Boot priority:
CD/DVD-ROM
On close:
Power off the VM
Console type:
vnc
Auto start console
Cancel
OK


QEMU VM template configuration
PVE
General settings
HDD
CD/DVD
Network
Advanced
Usage
HDA (Primary Master)
Disk image:
PVE-hda.qcow2
Browse...
Create...
Disk interface:
ide
HDB (Primary Slave)
Disk image:
Browse...
Create...
Disk interface:
none
HDC (Secondary Master)
Disk image:
Browse...
Create...
Disk interface:
none
HDD (Secondary Slave)
Automatically create a config disk on HDD
Disk image:
Browse...
Create...
Disk interface:
none
Cancel
OK


QEMU VM template configuration
PVE
General settings
HDD
CD/DVD
Network
Advanced
Usage
CD/DVD-ROM
Image:
/agmiar/GNS3/images/QEMU/proxmox-ve_8.4-1.iso
Browse...
Cancel
OK


QEMU VM template configuration
PVE
General settings
HDD
CD/DVD
Network
Advanced
Usage
Adapters:
2
First port name:
Name format:
eth{0}
Segment size:
0
Base MAC:
__:__:__:__:__:__
Type:
Paravirtualized Network I/O (virtio-net-pci)
Custom adapters:
Configure custom adapters
Replicate network connection states in Qemu
Use the legacy networking mode
Cancel
OK


QEMU VM template configuration
PVE
General settings
HDD
CD/DVD
Network
Advanced
Usage
Linux boot specific settings
Initial RAM disk (initrd):
Browse...
Kernel image:
Browse...
Kernel command line:
Bios
Bios image:
Browse...
Optimizations
Activate CPU throttling
Percentage of CPU allowed:
100 %
Process priority:
Normal
Additional settings
Options:
Enable Trusted Platform Module (TPM)
Enable UEFI boot mode
Use as a linked base VM
Cancel
OK


Proxmox VE 8.4 (iso release 1) - https://www.proxmox.com/
PROXMOX
Welcome to Proxmox Virtual Environment
Install Proxmox VE (Graphical)
Install Proxmox VE (Terminal UI)
Install Proxmox VE (Terminal UI, Serial Console)
Advanced Options
enter: select, arrow keys: navigate, e: edit entry, esc: back



Location and Time Zone selection

The Proxmox Installer automatically makes location-based optimizations, like choosing the nearest mirror to download files from. Also make sure to select the correct time zone and keyboard layout.

Press the Next button to continue the installation.


- **Country:** The selected country is used to choose nearby mirror servers. This will speed up downloads and make updates more reliable.
- **Time Zone:** Automatically adjust daylight saving time.
- **Keyboard Layout:** Choose your keyboard layout.

Country: Uruguay

Time zone: America/Montevideo

Keyboard Layout: U.S. English

Abort | Previous | Next


PROXMOX
Proxmox VE Installer
Administration Password and Email Address
Proxmox Virtual Environment is a full featured, highly secure GNU/Linux system, based on Debian.
In this step, please provide the root password.
Password: Please use a strong password. It must be at least 8 characters long, and contain a combination of letters, numbers, and symbols.
Email: Enter a valid email address. Your Proxmox VE server will send important alert notifications to this email account (such as backup failures, high availability events, etc.).
Press the Next button to continue the installation.
Password
Confirm
Email
da@estudiantes.utec.edu.uy
Abort
Previous
Next



Management Network Configuration

Please verify the displayed network configuration. You will need a valid network configuration to access the management interface after installing.

After you have finished, press the Next button. You will be shown a list of the options that you chose during the previous steps.

- **IP address (CIDR):** Set the main IP address and netmask for your server in CIDR notation.
- **Gateway:** IP address of your gateway or firewall.
- **DNS Server:** IP address of your DNS server.

A uno llamarlo pve-1.pft.test
Y al otro pve-2.pft.test

Management Interface	ens3 - 0c:b2:fd:f2:00:00 (virtio_net)
Hostname (FQDN)	pve.pft.test
IP Address (CIDR)	192.168.50.10 / 27
Gateway	192.168.50.1
DNS Server	192.168.50.12

Abort Previous Next




Summary

Please confirm the displayed information. Once you press the **Install** button, the installer will begin to partition your drive(s) and extract the required files.

Option	Value
Filesystem:	ext4
Disk(s):	/dev/sda
Country:	Uruguay
Timezone:	America/Montevideo
Keymap:	en-us
Email:	[redacted]@estudiantes.utec.edu.uy
Management Interface:	ens3
Hostname:	pve-1
IP CIDR:	192.168.50.10/27
Gateway:	192.168.50.1
DNS:	192.168.50.12

Automatically reboot after successful installation

Abort | Previous | Install




Elegir HDD

Luego ir a “CD/DVD”
Y borrar el nombre de
La ISO de Proxmox

“Apply” → OK → “Apply”

Asegurarse que la MAC de la interfaz sea la que está conectada al switch del CDA



nano /etc/hosts


192.168.50.10 pve-1.pft.test pve-1
192.168.50.11 pve-2.pft.test pve-2
192.168.90.28 pve-qdevice.pft.test pve-qdevice

Ctrl + X → “Y” → Enter

Para controlarlo desde SSH

---
systemctl enable --now ssh

(desde el SSH client)
ssh root@192.168.50.10



Crear un nuevo appliance para PVE-2, pero con
Hostname: pve-2.pft.test
IP: 192.168.50.11/27

Hacer las mismas verificaciones con PVE-2...

