

Cumi's Cheat mod collections

 nexusmods.com/dimraeth/mods/6



- [Games](#)
- [Dimraeth](#)
- [Mods](#)
- [Miscellaneous](#)
- Cumi's Cheat mod collections

- Endorsements

[5](#)

- Unique DLs

161

- Total DLs

387

- Total views

1,213

- Version

1

- Add media

- [Track](#)
- [Endorse](#)
- [Vote](#)
- Manage

- Download:

Last updated

20 September 2026, 3:16AM

Original upload

18 September 2026, 10:45PM

Created by

agungarifr

Uploaded by

[agungarifr](#)

Virus scan

Safe to use

Tags for this mod

- [Description](#)
- [Files 7](#)
- [Images 2](#)
- [Videos 0](#)
- [Posts 1](#)
- [Bugs 0](#)
- [Logs](#)

- [Stats](#)

About this mod

money_off This mod is currently not opted in to our mod rewards program. [Opt-in](#)

A collection of lightweight, zero-lag, highly configurable game breaking mods. Every feature is fully customizable via .cfg configuration files and is strictly applied only to the player character (monsters, bosses, and other entities remain untouched and balanced).

- [Share](#)
- [Report Abuse](#)

Requirements

Permissions and credits



You can use these mods individually or all together:

- PerfectParryMod (v1.1.1) — Complete rework and extension of the block/parry window with race-specific counter-attack triggers (Minotaur Retaliation, Human Counter-Attack, Rogue Vanish).
- AttackSpeedMod (v1.0.0) — Custom base attack speed and scaling multipliers exclusively for your character.
- AlwaysRegenMod (v1.4.0) — Continuous Health & Stamina regeneration with configurable multipliers, infinite sprint, and elimination of combat delay lockouts.
- CarryWeightMod (v1.0.0) — High-capacity or unlimited inventory weight limit across all interfaces (backpack, harvesting, looting, trading).
- LootAndExpMod (v1.1.0) — Multipliers for monster item drops, runes, dropped gold, combat EXP, quest rewards, and pet training with an optional 100% guaranteed drop rate.
- Autopickupmod -- its not auto, trigger dropped items pickup via space keyboard press on certain tile distance from your character. i hate clicking small objects.
- Chestmod -- modify chest and character inventory tile slots.

Requirements & Installation

Step 1: Install BepInEx 6 (IL2CPP Win-x64)

Download BepInEx-Unity.IL2CPP-win-x64 (v6.0.0-be or newer) from the official [BepInEx Builds](#) page. Extract the contents of the zip file directly into your Dimraeth game root directory (where Dimraeth.exe is located).

Your game folder should look like:

Dimraeth/

```

├── BepInEx/
├── dotnet/
├── Dimraeth.exe
├── doorstep_config.ini
└── winhttp.dll

```

Launch the game once to the main menu and exit. This generates necessary BepInEx interop assemblies and folders.

Step 2: Install the Mod(s)

Download the mod archive.

Place the desired .dll file(s) into your Dimraeth/BepInEx/plugins/ folder

Launch the game. The mods will automatically generate their respective .cfg files inside Dimraeth/BepInEx/config/.

⚙ Detailed Mod Breakdown & Configuration

1. PerfectParryMod (v1.1.1)

Vanilla parry timing in Dimraeth is extremely tight (~0.08 seconds / 80ms) and can be punishing due to network/animation frames. This mod lets you customize your parry window or enable guaranteed parrying while holding Right-Click/Block. It features automated triggers for all character race mechanics:

- Minotaur: Auto-triggers Retaliation shockwave explosion upon blocking an attack.
- Human / Standard: Auto-triggers Counter Attack strike.
- Rogue / Shadow: Auto-triggers Vanish evasion upon impact.

Configuration File: BepInEx/config/com.custom.perfectparrymod.cfg

Setting	Default	Description
<code>ModEnabled</code>	<code>true</code>	Enable / disable the mod.
<code>AlwaysPerfectParryWhileHolding</code>	<code>false</code>	When set to <code>true</code> , always triggers Perfect Parry / Retaliation / Vanish as long as you are holding block/Right-Click.
<code>CustomParryWindowSeconds</code>	<code>3.0</code>	Active when <code>Always...</code> is false. Extends the parry window from vanilla 0.08s to your chosen duration (e.g. 1.0s, 2.0s, 3.0s).
<code>MultiHitParry</code>	<code>true</code>	Allows repeated perfect parries / retaliations against rapid multi-hit combos during a single block hold.
<code>NoStaminaDrainOnParry</code>	<code>true</code>	Completely negates stamina loss when blocking within the parry window.

2. AttackSpeedMod (v1.0.0)

Customizes weapon swing and casting animation speeds. Fully integrated with character animations, status calculations, and character sheet UI.

Strictly Player-Exclusive: Bosses, enemy monsters, and NPCs will never gain attack speed from this mod.

Configuration File: BepInEx/config/com.custom.attackspeedmod.cfg

Setting	Default	Description
ModEnabled	true	Enable / disable the mod.
BaseAttackSpeed	1.50	Modifies base attack speed (Vanilla is 1.0). 1.50 provides +50% base speed.
AttackSpeedMultiplier	1.0	Additional multiplier applied to final attack speed (e.g., 1.2 for another 20% boost).
OnlyAffectLocalPlayer	true	Ensures changes only apply to your controlled player character.

3. AlwaysRegenMod (v1.4.0)

A robust health and stamina regeneration overhaul designed for continuous exploration and fluid combat without tedious downtime.

Eliminates the vanilla penalty where stamina and health regeneration stop while sprinting, attacking, or taking damage.

Configuration File: BepInEx/config/com.custom.alwaysregenmod.cfg

Setting	Default	Description
HealthRegenMultiplier	99.0	Multiplier applied to base health regeneration (e.g., 99.0x).
StaminaRegenMultiplier	99.0	Multiplier applied to base stamina regeneration (e.g., 99.0x).
InfiniteSprint	true	Reduces sprint stamina cost to 0, allowing unlimited sprinting.
NoRegenLockout	true	Removes the delay/lockout before regeneration begins after taking damage or casting.
ContinuousRegen	true	Unconditional 10Hz tick ensuring your HP and Stamina regenerate smoothly even during active attacks or spellcasting.

4. CarryWeightMod (v1.0.0)

Solves encumbrance bottlenecks by multiplying your carry weight limit across all game systems:

- Backpack UI capacity bar.
- Ground item pickup checks.
- Resource harvesting (mining, gathering, woodcutting).

- Vendor purchases & chest storage transfers.

Configuration File: `BepInEx/config/com.custom.carryweightmod.cfg`

Setting	Default	Description
<code>WeightMultiplier</code>	<code>99.0</code>	Multiplies your character's max carry weight (e.g. 50 kg becomes ~4,950 kg).
<code>UnlimitedCarryWeight</code>	<code>false</code>	When set to <code>true</code> , sets carry capacity to 1,000,000 (overrides multiplier).

5. LootAndExpMod (v1.1.0)

A progression and loot scaling mod to reduce repetitive grinding for rare items, gold, and character/pet levels.

Configuration File: `BepInEx/config/com.custom.lootandexpmod.cfg`

Setting	Default	Description
<code>ItemMultiplier</code>	<code>10</code>	Multiplies quantity of dropped items and runes from monsters (Default: 10x).
<code>GoldMultiplier</code>	<code>10</code>	Multiplies dropped gold quantity from monsters (Default: 10x).
<code>ExpMultiplier</code>	<code>30</code>	Multiplies EXP gained from combat kills, quest completions, events, and pet training (Default: 30x).
<code>GuaranteeMonsterDrops</code>	<code>true</code>	Forces a 100% drop chance on monster loot and rune tables.

6. Pickup Mod

- Spacebar Auto-Pickup:**
 - Pressing Space automatically collects all dropped items (`SimpleObject` items like weapons, armor, potions, crafting materials, and `RuneObject` runes) within range directly into your inventory.
 - Triggers the game's native inventory addition, pickup sound effects, and floating notification popups.
- Gold Vacuum:**
 - Automatically detects and vacuums dropped gold piles within the radius as well.
- Configurable Detection Radius:**
 - Default radius is `15.0` world units (covers the visible screen area around the character). You can increase or decrease this in the config.
- Typing Protection:**
 - Automatically ignores Space while typing in text input fields (chat box, chest rename, etc.) so you won't accidentally trigger item pickups while chatting.
- Input Dual-Support:**
 - Supports both Unity's legacy input and the new Unity Input System (`spaceKey.wasPressedThisFrame`), ensuring input is detected across all control configurations.
- Multiplayer Safe:**
 - Respects personal loot locks so only items intended for/available to you are collected.

Configuration Options

The config file will be created automatically in `BepInEx/config/com.custom.autopickupmod.cfg`:

Setting	Default	Description
<code>ModEnabled</code>	<code>true</code>	Enable or disable the Auto Pickup mod
<code>PickupRadius</code>	<code>15.0</code>	Radius in world units around your character
<code>TriggerKey</code>	<code>Space</code>	Keyboard key to trigger auto-pickup
<code>HoldToPickup</code>	<code>false</code>	If <code>true</code> , continuously vacuums while holding the key
<code>HoldPickupInterval</code>	<code>0.15</code>	Seconds between pulses when holding the key
<code>PickupGold</code>	<code>true</code>	Whether to also vacuum dropped gold piles
<code>LogPickups</code>	<code>false</code>	Log collected counts to the BepInEx console

7, Chestmod

1. All Chest Types Covered:
 - Applies to any chest in the game, including player-crafted chests (Pinewood Chest, Oak Cabinet, Heart Oak Chest, Chest Barrel, Basic Chest, and the Guildhall chest).
 - Routed automatically to the scrollable `LargeChest` view whenever slots exceed 18, ensuring smooth scrolling with UI slot generation.
 - Preserves your previously chosen 6x multiplier (108 slots).
2. Player Character Inventory Slot Expansion:
 - Hooks into character backpack capacity (`Inventory.GetBackpackSlotLimit` & `Inventory.CalculateVisibleBackpackSlots`).
 - Expands the backpack grid UI (`InventoryPaneView` & `Inventory.BackpackSlots`) with wired event triggers (left-click, right-click, middle-click, and hover).
 - Automatically pads the character's network inventory list (`Player.Inventory`) with empty entries so items pick up, sort, and place into expanded slots without index errors.
 - Dynamically expands the scroll container height (`_backpackScrollContent`) so you can scroll down through all your extra inventory slots.

```

#### Configuration File
File location: com.custom.rahanerchestmod.cfg

[Chests]
## If true, expands all chests (crafted pinewood/oak/heart oak chests, barrels, cabinets, basic chests, guildhall).
ApplyToAllChests = true

## Multiplier applied to chest tile slots (e.g. 2.0 = 36 slots, 3.0 = 54 slots, 6.0 = 108 slots).
ChestSlotMultiplier = 6

## Exact slot override for chests (e.g. 54, 72, 90, 108). Set to -1 to use ChestSlotMultiplier.
ChestCustomSlots = -1

## Set to true if you ever want to restrict it ONLY to the Guildhall chest next to Rahaner.
TargetOnlyRahanerChest = false

[PlayerInventory]
## If true, expands your character's inventory tile slots.
EnablePlayerInventoryExpansion = true

## Multiplier applied to your backpack slots (e.g. 1.5 = 1.5x, 2.0 = 2x, etc.).
PlayerSlotMultiplier = 2

## Exact slot override for player inventory (e.g. 48, 60, 72, 84, 96, 120). Set to -1 to use PlayerSlotMultiplier.
PlayerCustomSlots = -1

[General]
EnableLogging = true

```

? Frequently Asked Questions (FAQ)

- Q: How do I change settings or turn off specific features?
- A: Open the .cfg files located in Dimraeth/BepInEx/config/ using any text editor (Notepad, VS Code). Adjust the numbers or change true/false, then save. Restart the game to apply changes.
- Q: Will this affect enemies or make bosses overpowered?
- A: No. All modifications (Attack Speed, Regen, Encumbrance, Parry mechanics) contain strict filters targeting only Player / IsPlayer / IsOwner instances.
- Q: Can I pick and choose which mods to install?
- A: Yes. Each mod .dll is completely standalone. Only put the .dll files you want into BepInEx/plugins/.