


```
ROUTER
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status      Prot
o0/0
Ethernet0/0      unassigned      YES TFTP   up          up
Ethernet0/1      unassigned      YES TFTP   down        down
Ethernet0/2      unassigned      YES TFTP   down        down
Ethernet0/3      unassigned      YES TFTP   down        down

ROUTER#configure t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#exit
ROUTER#co
*Jul 13 07:40:28.840: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#interface e0/0
ROUTER(config-if)#ip address 10.0.0.1 255.0.0.0
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Jul 13 07:42:30.294: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status      Prot
o0/0
Ethernet0/0      10.0.0.1        YES manual up          up
Ethernet0/1      unassigned      YES TFTP   down        down
Ethernet0/2      unassigned      YES TFTP   down        down
Ethernet0/3      unassigned      YES TFTP   down        down

ROUTER#ping 10.0.0.2
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.0.0.2, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/2 ms
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#line console 0
ROUTER(config-line)#password 123
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
```




```
ROUTER
ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: 123
Password:
ROUTER>enable
Password:
ROUTER#config t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#login
% Login disabled on line 2, until 'password' is set
% Login disabled on line 3, until 'password' is set
% Login disabled on line 4, until 'password' is set
% Login disabled on line 5, until 'password' is set
% Login disabled on line 6, until 'password' is set
ROUTER(config-line)#login local
ROUTER(config-line)#
*Jul 13 07:57:39.489: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up
*Jul 13 07:57:40.490: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up
ROUTER(config-line)#
*Jul 13 07:57:49.490: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to down
*Jul 13 07:57:50.490: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to down
ROUTER(config-line)#
*Jul 13 07:57:53.278: %SYS-5-CONFIG_I: Configured from console by 123 on vty0 (10.0.0.2)
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#config t
*Jul 13 07:59:14.485: %SYS-5-CONFIG_I: Configured from console by 123 on console
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status      Protocol
Ethernet0/0    10.0.0.1        YES manual up          up
Ethernet0/1    20.0.0.1        YES manual down        down
Ethernet0/2    unassigned      YES TFTP  down        down
Ethernet0/3    unassigned      YES TFTP  down        down
ROUTER#
```




```
ROUTER

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: 123
Password:
ROUTER>enable
Password:
ROUTER#config t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#login
% Login disabled on line 2, until 'password' is set
% Login disabled on line 3, until 'password' is set
% Login disabled on line 4, until 'password' is set
% Login disabled on line 5, until 'password' is set
% Login disabled on line 6, until 'password' is set
ROUTER(config-line)#login local
ROUTER(config-line)#
```



```
ROUTER

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Password:
ROUTER#config t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#username 123 password 123
ROUTER(config)#line console 0
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#e
*Jul 13 07:51:53.057: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#exit
```

