xCircuit3_skillDisplay.md 2020/7/18

About

位置 (-1920,16,-189)

呼び出し元 毎tick実行するコマンド群3

現在設定されているスキルについて表示を行う。

コマンド群

No.	コマンド	状 態
1	/tellraw @a[score_ShowSkillSlot_min=4,score_ShowSkillSlot=4,score_ModeState_min=1] {"translate":"現在のモードスキル設定(%1\$s中) %2\$s/%3\$s","bold":true,"with":[{"text":"ルビーモード","color":"red"},{"text":"↓","color":"blue"}]}	
2	/tellraw @a[score_ShowSkillSlot_min=4,score_ShowSkillSlot=4,score_ModeState=-1] {"translate":"現在のモードスキル設定(%1\$s中) %2\$s/%3\$s","bold":true,"with":[{"text":"サファイアモード","color":"blue"},{"text":"↑","color":"blue"}]}	
3	/tellraw @a[score_ShowSkillSlot_min=4,score_ShowSkillSlot=4,score_ModeState_min=0,score_ModeState=0] {"translate":"現在のモードスキル設定(%1\$s中) %2\$s/%3\$s","bold":true,"with":[{"text":"モード未設定","color":"gray"},{"text":"↑","color":"blue"}]}	
4	/execute @a[score_ShowSkillSlot_min=4,score_ShowSkillSlot=4] $\sim \sim \sim$ /scoreboard players operation @a[c=1] ShowSkill = @a[c=1] ModeSkillA	
5	/execute @a[score_ShowSkillSlot_min=3,score_ShowSkillSlot=3] $\sim \sim \sim$ /scoreboard players operation @a[c=1] ShowSkill = @a[c=1] ModeSkillB	
6	/tellraw @a[score_ShowSkillSlot_min=2,score_ShowSkillSlot=2] {"translate":"現在のサポートスキル 設定 %1\$s/%2\$s","bold":true,"with":[{"text":"↑","color":"red"},{"text":"↓","color":"blue"}]}	
7	/execute @a[score_ShowSkillSlot_min=2,score_ShowSkillSlot=2] $\sim \sim \sim$ /scoreboard players operation @a[c=1] ShowSkill = @a[c=1] InstantSkillA	条 件 付 き
8	/execute @a[score_ShowSkillSlot_min=1,score_ShowSkillSlot=1] $\sim \sim \sim$ /scoreboard players operation @a[c=1] ShowSkill = @a[c=1] InstantSkillB	
9	/scoreboard players remove @a[score_ShowSkillSlot_min=1] ShowSkillSlot 1	

詳細

- 1. ShowSkillSlotが4であり、ModeStateが1以上であるすべてのプレイヤーに現在のルビーのモードスキル設定を表示
- 2. ShowSkillSlotが4であり、ModeStateが-1以下であるすべてのプレイヤーに現在のサファイアのモードスキル設定を表示

xCircuit3 skillDisplay.md 2020/7/18

3. ShowSkillSlotが4であり、ModeStateが0であるすべてのプレイヤーにモード未設定時の現在のモード スキル設定を表示

- 4. ShowSkillSlotが4であるプレイヤーのShowSkillにModeSkillAを代入
- 5. ShowSkillSlotが3であるプレイヤーのShowSkillにModeSkillBを代入
- 6. ShowSkillSlotが2であるすべてのプレイヤー現在のサポートスキル設定を表示
- 7. ShowSkillSlotが2であるプレイヤーのShowSkillにInstantSkillAを代入
- 8. ShowSkillSlotが1であるプレイヤーのShowSkillにInstantSkillBを代入
- 9. ShowSkillSlotが1以上であるすべてのプレイヤーのShowSkillSlotから1を引く