

```
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#exit
ROUTER#
*Jul 13 03:55:27.674: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
```

| Interface   | IP-Address | OK? | Method | Status | Prot |
|-------------|------------|-----|--------|--------|------|
| Ethernet0/0 | unassigned | YES | TFTP   | up     | up   |
| Ethernet0/1 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/2 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/3 | unassigned | YES | TFTP   | down   | down |

```
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1
% Incomplete command.
```

```
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Jul 13 03:57:25.553: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
```

| Interface   | IP-Address | OK? | Method | Status | Prot |
|-------------|------------|-----|--------|--------|------|
| Ethernet0/0 | 50.0.0.1   | YES | manual | up     | up   |
| Ethernet0/1 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/2 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/3 | unassigned | YES | TFTP   | down   | down |

## User Access Verification

Username: akilan

Password:

ROUTER>ping 50.0.0.10

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:

.!!!!

Success rate is 80 percent (4/5), round-trip min/avg/max = 1/1/2 ms

ROUTER>enable

Password:

ROUTER#show ip interface brief

| Interface   | IP-Address | OK? | Method | Status | Prot |
|-------------|------------|-----|--------|--------|------|
| ocol        |            |     |        |        |      |
| Ethernet0/0 | 50.0.0.1   | YES | manual | up     | up   |
| Ethernet0/1 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/2 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/3 | unassigned | YES | TFTP   | down   | down |

ROUTER#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#line vty 0 4

ROUTER(config-line)#transport input telnet

ROUTER(config-line)#password akilan

ROUTER(config-line)#login

ROUTER(config-line)#exit

ROUTER(config)#