


Subnetting project-5

-Akilan D

Step 1:Assign IP for routers and create pool for Dhcp to Assign ip Dyamically for the Pc's



```
R5#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int eth 0/0
R5(config-if)#ip add 129.70.1.66 255.255.255.252
R5(config-if)#no sh
R5(config-if)#exit
R5(config)#int eth 0/1
R5(config-if)#ip add 12
*Aug 17 11:16:42.562: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R5(config-if)#ip add 129.70.1.1 255.255.255.192
R5(config-if)#no sh
R5(config-if)#exit
R5(config)#sh ip int bri
% Invalid input detected at '^' marker.
R5(config)#exit
R5#sh ip
*Aug 17 11:17:23.190: %SYS-5-CONFIG_I: Configured from console by console
R5#sh ip int bri
Interface                IP-Address      OK? Method Status    Prot
Ethernet0/0              129.70.1.66     YES manual up        up
Ethernet0/1              129.70.1.1      YES manual up        up
Ethernet0/2              unassigned      YES TFTP  down      down
Ethernet0/3              unassigned      YES TFTP  down      down
R5#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int eth 0/1
R5(config-if)#ip helper-address 129.70.1.65 255.255.255.252
% Invalid input detected at '^' marker.
R5(config-if)#ip helper-address 129.70.1.65
R5(config-if)#
```


 R3

```
R3#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#int eth 0/1
R3(config-if)#ip add 12.0.1.154 255.255.255.248
R3(config-if)#no sh
R3(config-if)#exit
R3(config)#int eth 0/0
R3(config-if)#ip add 12.0.0.1 255.255.255.0
R3(config-if)#no sh
R3(config-if)#exit
R3(config)#int eth 0/0
R3(config-if)#ip helper-address 12.0.1.153
R3(config-if)#exit
R3(config)#
*Aug 18 04:30:48.476: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R3(config)#
```

 R1

```
R1#
R1#
R1#'
% Bad IP address or host name
% Unknown command or computer name, or unable to find computer address
R1#'
% Bad IP address or host name
% Unknown command or computer name, or unable to find computer address
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#in eth 0/1
R1(config-if)#ip add 12.0.1.146 255.255.255.252
R1(config-if)#no sh
R1(config-if)#exit
R1(config)#in eth 0/1
R1(config-if)#exit
R1(config)#in eth 0/0
R1(config-if)#ip add 12.0.0.1 255.255.255.0
R1(config-if)#no sh
R1(config-if)#ip helper-address 12.0.1.145
R1(config-if)#exit
R1(config)#
```

```

Router#sh ip dhcp pool
Pool 1stfloor-nt :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 62
  Leased addresses                  : 1
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    129.70.1.3         129.70.1.1 - 129.70.1.62 1
Pool 2ndfloor-nt :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 254
  Leased addresses                  : 1
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    129.70.0.3         129.70.0.1 - 129.70.0.254 1
Pool 1stfloor-sn :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 14
  Leased addresses                  : 0
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    12.0.1.141         12.0.1.129 - 12.0.1.142 0
Pool 3rdfloor-nt :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 254
  Leased addresses                  : 2
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    12.0.0.4           12.0.0.1 - 12.0.0.254 2
Pool 2ndfloor-sn :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 62
  Leased addresses                  : 1
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    12.0.1.3           12.0.1.1 - 12.0.1.62 1
--More--

```

```

12.0.1.141      12.0.1.129      - 12.0.1.142      0
Pool 3rdfloor-nt :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 254
  Leased addresses                  : 2
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    12.0.0.4           12.0.0.1 - 12.0.0.254 2
Pool 2ndfloor-sn :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 62
  Leased addresses                  : 1
  Pending event                     : none
  1 subnet is currently in the pool :
    Current index      IP address range      Leased addresses
    12.0.1.3           12.0.1.1 - 12.0.1.62 1
Pool 1stfloor-sn :
  Utilization mark (high/low)      : 100 / 0
  Subnet size (first/next)         : 0 / 0
  Total addresses                   : 0
  Leased addresses                  : 0
  Pending event                     : none
  0 subnet is currently in the pool
Router#
Router#
Router#
Router#
Router#
Router#
Router#
Router#
Router#sh ip int bri
Interface      IP-Address      OK? Method Status      Protocol
Ethernet0/0    12.0.1.145      YES manual up          up
Ethernet0/1    12.0.1.149      YES manual up          up
Ethernet0/2    12.0.1.153      YES manual up          up
Ethernet0/3    129.70.1.65     YES manual up          up
Ethernet1/0    129.70.1.69     YES manual up          up
Ethernet1/1    unassigned      YES unset administratively down down
Ethernet1/2    unassigned      YES unset administratively down down
Ethernet1/3    unassigned      YES unset administratively down down
Router#

```


Step 2: Switch on the pc and restart the nic card to get dynamic IP

