

KNOWLEDGE ARTICLE

VPN Connection and Remote Access Troubleshooting

Intent key	VPNConnectionIssues	Category	Network and Remote Access
Routing	Bedrock Knowledge Base / LLM fallback	Lex overlap	No direct match in the supplied intent workbook

Purpose and intent scope

Use this article when a user cannot connect to the corporate VPN, the VPN repeatedly disconnects, or internal resources remain unavailable after connection.

Suggested answer

I can help troubleshoot the VPN. First confirm that your normal internet connection works, then restart the VPN client and reconnect using your current corporate credentials. Check that your device time is correct and complete MFA promptly. If the issue continues, restart the device and test from another trusted network. Please share the exact error message, VPN client, operating system, and whether the problem happens on another network.

Common user utterances

- I cannot connect to the VPN.
- The VPN keeps disconnecting every few minutes.
- VPN authentication succeeds but internal sites do not open.
- I am getting a VPN timeout error.
- Remote access is not working from home.
- The VPN client says no network connection.
- I connected to VPN but cannot reach the shared drive.
- My VPN stopped working after a password change.

Recommended troubleshooting sequence

1. Confirm that the normal internet connection works by opening a public website. If the internet itself is unavailable, fix the local Wi-Fi or wired connection first.
2. Close and reopen the VPN client. Make sure only one VPN client session is running.
3. Verify that the device date, time, and time zone are correct. Incorrect time settings can cause certificate and authentication failures.
4. Enter the current corporate username and password. After a recent password change, sign out of the VPN client completely and reconnect with the new password.
5. Complete multi-factor authentication promptly. If the approval notification expires, start a new connection attempt.
6. Restart the computer and home router when the client continues to time out or disconnect.
7. Try a different trusted network, such as a mobile hotspot, to determine whether the current network is blocking VPN traffic.
8. After connecting, wait up to one minute and then retry the internal website, shared drive, or remote desktop destination.

Security and safety boundaries

Do not recommend the following actions:

- Do not disable endpoint protection, firewall, or device-management software.
- Do not install an unapproved VPN client.
- Do not share passwords, one-time codes, or screenshots containing security tokens.

When to escalate

- The VPN client shows a certificate, device-compliance, account-disabled, or access-denied error.
- Multiple users are unable to connect at the same time.
- The issue continues on more than one trusted network after a restart.
- The user can connect, but a specific internal system remains unavailable.

Information to collect for support

- Exact error message and error code
- Approximate time of the failed attempt
- VPN client name and version
- Operating system and device type
- Whether the issue occurs on another network
- Name of the internal resource that cannot be reached

Routing guidance for the assistant

Use this article when the request clearly matches the intent scope. Provide the suggested answer, then guide the user through the troubleshooting steps in order. Ask only for non-sensitive diagnostic details. If an escalation condition is met, recommend creating a support request and include the collected details. Never request passwords, MFA codes, private keys, or security tokens.

Knowledge-base note

This article was intentionally created for a topic not directly represented in the supplied Lex intent list. It is suitable for retrieval by an LLM fallback or Amazon Bedrock Knowledge Base. Internal service-desk URLs, approved software names, and organization-specific escalation paths should be added only after validation.