

KNOWLEDGE ARTICLE

Microsoft Teams Microphone, Speaker, and Camera Issues

Intent key	TeamsAudioVideoIssues	Category	Meetings and Collaboration
Routing	Bedrock Knowledge Base / LLM fallback	Lex overlap	No direct match in the supplied intent workbook

Purpose and intent scope

Use this article when a user cannot hear others, cannot be heard, has no camera image, experiences echo, or Teams is using the wrong audio or video device.

Suggested answer

Check the physical mute control, then open Teams Settings > Devices and select the correct microphone, speaker, and camera. Run a test call or preview, reconnect the device, and close any other application using the camera or microphone. Verify operating-system privacy permissions, then restart Teams. For echo, use one audio-enabled device and preferably a headset.

Common user utterances

- My microphone is not working in Teams.
- People cannot hear me in a meeting.
- I cannot hear anyone in Teams.
- My camera is black in Teams.
- Teams is using the wrong headset.
- There is an echo during meetings.
- My camera works in other apps but not Teams.
- The test call has no audio.

Recommended troubleshooting sequence

1. Check the physical mute button on the headset, keyboard, or microphone. Also confirm that the Teams meeting mute control is off.
2. In Teams settings, open Devices and choose the intended speaker, microphone, and camera.
3. Run a Teams test call when available, or check the device preview before joining the meeting.
4. Disconnect and reconnect USB or Bluetooth devices. For Bluetooth headsets, verify that the headset is connected for both audio input and output.
5. Close other applications that may be using the camera or microphone, such as another meeting or recording application.
6. Check operating-system privacy settings and ensure Teams is allowed to use the microphone and camera.
7. Leave and rejoin the meeting. If the problem continues, restart Teams and then restart the computer.
8. For echo or feedback, use a headset, lower speaker volume, and avoid joining the same meeting from two nearby devices with audio enabled.

Security and safety boundaries

Do not recommend the following actions:

- Do not share meeting links, recordings, or participant information outside approved channels.
- Do not install unapproved virtual audio or camera drivers.
- Do not change organization-wide Teams settings.

When to escalate

- The camera or microphone is missing from both Teams and operating-system device settings.
- The issue persists with a second known-good headset or camera.
- Teams reports an administrative policy or permission error.
- Many meeting participants have the same audio or video failure.
- The application crashes whenever a meeting starts.

Information to collect for support

- Meeting date and approximate time
- Device selected in Teams settings
- Whether the device works in another application
- Teams version and operating system
- Whether the issue affects every meeting
- Screenshot of the error without sensitive meeting content

Routing guidance for the assistant

Use this article when the request clearly matches the intent scope. Provide the suggested answer, then guide the user through the troubleshooting steps in order. Ask only for non-sensitive diagnostic details. If an escalation condition is met, recommend creating a support request and include the collected details. Never request passwords, MFA codes, private keys, or security tokens.

Knowledge-base note

This article was intentionally created for a topic not directly represented in the supplied Lex intent list. It is suitable for retrieval by an LLM fallback or Amazon Bedrock Knowledge Base. Internal service-desk URLs, approved software names, and organization-specific escalation paths should be added only after validation.