

AcME ERP Deployment Scheme

AcME ERP is deployed under two models.


1. Standard Model

AcME ERP is given as client-server windows application. All accounting functions can be done at a single node or multiple nodes. The system can be configured for a single user or multiple users with a single database.

2. Enterprise Model

Along with the client-server windows application (for individual Branch Offices), AcME ERP provides cloud-based application service via the internet. This edition provides access at the Head Office level to have consolidated financial reports from all Branch Offices. It is also possible to track the status of an individual Branch Office. The data from the individual Branch Offices shall be periodically updated to the Head Office. If the particular institute (Branch Office) does not have internet facility, the data can be exported in electronic format and uploaded from wherever internet connection is available.

3. Deployment Model



4. Procedures

Standard Model

Standard Model will be deployed in every institution (Branch Office) as a Stand-alone or client Server. The Setup files will be downloaded from the web portal and configured in the local machine.

Configuration

Branch Office	Hardware
	Processor : Intel® Core™ i3/i5 processor or above
	Ram : 4 GB or Above
	HDD : 500 GB or Above
	Operating System : Windows 7 and above
	Software : MySQL, .Net Framework

Enterprise Model

Enterprise Model will be deployed in the Cloud for every provinces opt for it. This process happens automatically and does not require any configuration.

AcME ERP Admin Portal shall create the username and password for the each provinces. The provinces can have multiple branch office.

AcME ERP portal

Each branch offices can have user name, password. They can login to the account and push the data to AcME ERP portal if opted for offline synchronization. The Head Office can view all the branch office data.

Application /Database Server

AcME ERP Dedicated Windows servers keep in US. Application and Database servers are maintained in the same server.

Configuration and Server Price

Dedicated Server	Hardware
	Processor : Intel@ Core TM i5 -4 Cores
	Ram : 8 GB
	HDD :2 x 2 TB
	Operating System :Windows 2008 R2 64-Bit
	Software : MySQL, .Net Framework

Add-ons

Bandwidth	: None
Control Panel	: None
Software	: None
Firewall	: +Cisco ASA 5505 Firewall
MS SQL Database	: None
FTP Backup	: None
Managed Backup	: Daily Managed
RAID 1	: + RAID 1

Volume Handling

The architecture will support multiple database file servers. In the event of server failure, users connected to this server will start working on other server without interruption. The failed server can be set right and reconnected

Security

SSL (Secure Socket Layer) : Is a standard security technology for establishing an encrypted link between a server and a client-typically a web server and a browser or a mail server and mail client

Data Synchronization

Synchronization between standard and Enterprisemodel shall be defined as a parameter of the license. The Branch office data can be synchronize and uploaded to the Acme.

Trouble Ticket Submit Controller

AcME ERP trouble tickets submit controller is used to post the problems to the customer care automatically.

Version Update Controller

Version update controller is used to fetch the updates from AcME ERP portal and update in to local system.

AcME ERP Admin Portal

System Admin /Business Admin

Creates a Head Office with Head Office Admin, User ID, Password, Maximum Number of Licenses and Maximum Number of Nodes, Order Value and Date of Renewal.

Head Office Admin

Creates each Branch Office with Branch Office Admin, User ID, Password, Maximum Number of Nodes, Maximum Number of Users.

Branch office Admin

Creates Branch office Users at the Portal Level and Rights for Branch office Level

Head Office User

Auditors can view the Consolidate Reports and Post the Trouble Tickets and Send Amendment Notes

Branch Office User

Branch Office users View Branch Level Reports

License Renewal

Based on the Financial Year the license file shall be created.

- Validate the Expiry date
- The License renewal alert message should display before 60days in the Home page.
- Need to specify the alert while login for expiry for the financial year.
- Based on the Customer Id the License renewal will be activated and sent to the customer to updating the license file.

License Expiry

Every Transaction date will be validated based on the license date

After the expiry date, only reports can be viewed and printouts can be taken. Whenever user clicks the reports License Expiry message should be display.

Installation Procedures

1. Customer would request for the AcME ERP application with institution details with no of license.
2. System Admin /Business Admin will generate Username & Password in the Admin Portal and send it to the Customer.
3. Customer would login to <http://www.acmeerp.org/> to download the AcME ERP application.
4. After downloading the build from the portal, Customer would do the Installation.
5. Customer based patches available in the admin portal.

Server Installation

1. Customer would run the Downloaded AcME ERP Setup.
2. Installation process would ask customer to select Server/ Client installation.
3. Customer has to select Server for server installation.
4. Installation process would send Customer's Details and its License details to Acme++ Portal and check whether the customer is valid or installed already.
4. Installation process would create the Database automatically for server installation.
5. After finishing the server installation, Entry (Server details) would be made in the admin portal to avoid multiple server installation.
6. If there is a new patch in the Admin portal for the customer. It would ask the customer to update. Customer could update anytime.
7. Server would maintain the Registry Node for Client.

Note: Sever should connect with Internet for server installation.

Server Uninstall

1. Uninstallation process would uninstall the AcME ERP Application. It would remove the Sever Node Registry automatically. And it would communicate to the admin portal to remove the registry information in the admin portal.
2. In case of hardware failure or System crash, Customer has to approach the AcME ERP deployment team to get the AcME ERP Application from the admin portal.

Client Installation

1. Customer would run the downloaded AcME ERP setup.
2. Installation process would ask for Server/Client Installation.
3. Customer has to select Client for Client installation.
4. Installation process would list the list of servers available in the system.
4. Customer has to select AcME ERP server from the List.
4. Installation process would check the Node registry in the server, If Number of node exceeds It would pop up to the customer. "Number of node exceeds". Uninstall any of the clients for installation.
5. After finishing the Installation, Entry would be made in the Server Registry Node to keep track no of client register to this server.


Client Uninstall

Uninstallation process would allow customer to uninstall the client and also it would automatically remove the sever node registry in the Server.

Backup

Restore

ACPP Branch Installation Process



Claim Support

Online Support

Online support is the assistance provided to you at your office via support centre, email and telephone. We believe that these online options will help resolve your concerns in the fastest and most efficient manner.

AcME ERP provides all the basic services for the customers to use it efficiently. Customer support includes assistance in planning, installation, training, trouble shooting, maintenance, upgrading, and disposal of a product. These services reduce the work load of the customer in all the activities.

A full time customer support is provided by which the customer can reach Bosco Soft at any time for any clarification in the product.

When a customer has any problems in system, he/she approaches the customer care and complains about system problems. The customer care registers the particular customer's complaints with docket number.

The customer care teams try to solve the problems through online. The following online services are provided.



1. Team viewer, Remote Login or Ammy Admin (This model will fit for Standard Model)
2. Email Support : customercare@boscosofttech.com
3. Tele Support : + 91 96 26 800 800

Onsite support



The customer care makes a trip request to customer onsite, assign a staff for that trip and specify a trip date.

The customer support staff takes a trip to customer onsite and solves the problems.

The training session for the staff at the client site is coordinated by Bosco through the Customer Care Executives.

The staff prepares a trip report on specified date if the customer's complaints are resolved; if not, the staff prepares a bug report. In case, customers request for any enhancements in system, the staff considered as change request.

The following activities are following by the Customer Support Team when the customer gets trouble in system. Once all the activities are taken place, it will be address to the customer get reviewed by the customer.

- Requirements/Reviews from the Customer Care Team
- Effort & Impact Analysis
- plan & Schedule
- Development
- Reviews (External)
- Testing & Verification
- Deployment (By CC Executives)