Talos User Management

Talos User Management

While GCXONE manages the account identity, Talos handles the behavioral settings of how an operator interacts with alarms.

For more detailed information about Talos user management, visit the Evalink Documentation at documentation.evalink.io

Users Overview

Users are company members and other individuals who can work in Talos under the Company account.

Talos operates the following user-related terms:

- User Roles
- User Types
- User Profiles

Only Administrators can invite and manage users, create new User Roles and User Types.

User Roles

Each user has a role that defines their level of permissions. There are four preset User Roles in Talos. They cannot be changed or deleted.

Administrators can also create custom User Roles based on the preset User Roles. A custom User Role allows you to configure a custom set of permissions.

You can view all User Roles for your company under Company → Settings → Users.

The following preset User Roles exist in Talos:

Administrator Has a full set of permissions. There can be several Administrators under one Company.

Manager Intended for managing the work of users with Operator and Operator Minimal User Roles. Like Administrator, Manager can create and manage major Talos objects such as workflows, sites, site groups, and schedules, but access to some features is restricted. For example, Manager cannot invite users or edit global alarm settings.

Operator Intended for alarm processing. Operator has access to all Talos interface pages but for the most part cannot create or manage objects — only has permissions for viewing.

Operator Minimal Also intended for alarm processing. Compared to Operator, Operator Minimal has access to a limited number of interface pages.

Both Operator and Operator Minimal can create and edit certain Talos objects if required to do so by a workflow — for example, if the Add Schedule Entry step is included in a manual workflow.

User Types

User Types allow fine-tuning of user experience by combining User Roles with certain pre-configured work environments such as Test Types and Workspaces, and access permissions such as selected access to Site Groups in your company.

User Types narrow down the flow of incoming alarms for each user in order to more effectively distribute alarms between available operators.

There are four preset User Types in Talos. They cannot be deleted, but Administrators can change their settings. Administrators can also add and delete custom User Types.

The following preset User Types exist in Talos:

Administrator Default User Role: Administrator. Default Workspace: Default. Default Test Type: System.

Manager Default User Role: Manager. Default Workspace: Default. Default Test Type: System.

Operator Default User Role: Operator. Default Workspace: Default. Default Test Type: System.

Operator Minimal Default User Role: Operator Minimal. Default Workspace: Default. Default Test Type: System.

Note: User Role is a kernel setting that defines available user permissions. User Type is the main user-defining quality — it combines a User Role and available working environments (Workspaces and Test Types). When Administrators invite new users, they select a User Type for them when issuing an invite.

User Profiles

A User Profile is the Talos user interface page where you can view all your user information and manage your user activity.

To access your user profile, click the user profile icon in the upper right corner and select Profile from the dropdown menu.

The following tabs are available on the User Profile page:

Profile: View all your user details, monitor and manage your user activity and sessions, and perform basic user actions.

Company Management: View which companies you are a member of, accept invites, and switch between companies without logging out and back in.

How Users Are Created

To create a new user, an Administrator sends an invite to the user. The only prerequisite required is a valid email address. The user then logs in to Talos following the instructions in the invitation and verification emails.

After the first user login, the record of the user appears in the list on Company → Users.

When inviting a user, the Administrator selects a User Type from the list of available types which includes preset and custom User Types. After a user accepts the invite and logs in, Administrators can change their User Type.

Managing Your User Profile

Change User Name

1. In the Profile tab of the User Profile page, scroll to Profile Actions and select Change Name.
2. Type your First Name and Last Name in the corresponding fields. Both fields are required. You must enter at least 3 characters for each.
3. Click Let's Start. Talos will log you out for the changes to take effect. Log back in to continue.

Change User Password

1. In the Profile tab, scroll to Profile Actions and select Change Password. Talos sends an email to your login address.
2. Follow the link in the email.
3. Enter your new password in both fields so they match. Your password must be at least 8 characters long and include lower and upper case letters, numbers, and special symbols.
4. Click the arrow to confirm. Talos will log you out. Log back in using your new password to continue.

Viewing Your Sessions

You can log into Talos simultaneously from several devices, locations, or web browsers. Each login instance is considered a session. All current sessions are displayed in your user profile with the following properties:

- IP Address: The IP address from which you are logged in. Your current session is marked [You].
- Last Access: The time when this session was last active.
- Location: The approximate location narrowed down to a country and city.
- Browser: The operating system and browser name and version used to log in.
- Fingerprint: A unique stamp marking each individual session.

Invalidate Sessions

You can simultaneously log out of Talos from all current sessions on all devices using the Invalidate Sessions option.

To invalidate all sessions, click the Invalidate Sessions icon at the bottom-right of the page, or use the Invalidate Sessions option in the If your Account Has Been Compromised area. Talos terminates all existing sessions. You will need to log back in to continue work.

Company Management

If you belong to more than one company, the Company Management tab contains all information on the companies you are a member of, including pending invitations.

Join Another Company

To become a member of a company, you must receive an invitation from that company's Administrator. You must accept the invite within 7 days of receiving it, otherwise it will expire.

1. In the Company Management tab, view the list of pending invitations.
2. Click the checkmark icon next to the company name you want to join.
3. Talos adds the company to your list. Use the Switch Company button to switch to the new company.

To decline an invitation, click the X icon next to the invite. Note that if you decline and then decide to join, you will need to receive a new invite.

Switching Between Companies

In the Company Management tab, click the Switch button next to the company you want to switch to.

Leave a Company

1. Click the Leave the Company icon at the bottom-right of the page.
2. Confirm by clicking Yes.

When you belong to several companies, leaving one deletes your user record from that company only. You will remain a user of your other companies. An Administrator can invite you back after you leave.

Managing Users

Invite a User Navigate to Company → Users and click Invite User.

Search for a User Use the search function on the Company → Users page.

Edit a User

1. Navigate to Company → Users.
2. Click on the user you want to edit.
3. Update their User Type or other settings.
4. Save changes.

Delete a User

1. Navigate to Company → Users.
2. Click on the user you want to delete.
3. Confirm the deletion.

How the Systems Sync

Talos uses your GCXONE user account as the base for its sessions. However, once a user enters the Talos interface, their permissions are governed by Talos Roles and User Types.

Identity: GCXONE manages email and MFA. Talos leverages the GCXONE session.

Platform Access: GCXONE manages permissions to see Configuration. Not applicable in Talos.

Workflow: Not applicable in GCXONE. Talos manages permissions to view, process, or close alarms.

Behavior: Not applicable in GCXONE. Talos manages automatic redirection and auto-assign rules.

Troubleshooting Access

Login Loops: If an operator can see GCXONE but gets a Permission Denied error in Talos, ensure they have been assigned a Talos Role in Company → Users settings.

Missing Alarms: Verify the operator is part of the correct Alarm Group for the site in question.