```
UDP client
```

```
from socket import *
serverName = 'localhost'
serverPort = 12000
clientSocket = socket(AF INET, SOCK DGRAM)
message = raw input('Input lowercase sentence:')
clientSocket.sendto(message, (serverName, serverPort))
modifiedMessage, serverAddress = clientSocket.recvfrom(2048)
print modifiedMessage
clientSocket.close()
UDP server
from socket import *
serverPort = 12000
serverSocket = socket(AF INET, SOCK DGRAM)
serverSocket.bind(('', serverPort))
print "The server is ready to receive"
while 1:
    message, clientAddress = serverSocket.recvfrom(2048)
    print "Datagram from: ", clientAddress
    modifiedMessage = message.upper()
    serverSocket.sendto(modifiedMessage, clientAddress)
UDP error management
from socket import *
serverName = 'localhost'
serverPort = 12001
clientSocket = socket(AF INET, SOCK DGRAM)
clientSocket.settimeout(5)
message = raw input('Input lowercase sentence:')
try:
    clientSocket.sendto(message, (serverName, serverPort))
    modifiedMessage, serverAddress = clientSocket.recvfrom(2048)
    # in case of error blocks forever
    print modifiedMessage
except error, v:
   print "Failure"
    print v
finally:
    clientSocket.close()
TCP client
from socket import *
serverName = 'localhost'
serverPort = 12000
clientSocket = socket(AF INET, SOCK STREAM)
clientSocket.connect((serverName, serverPort))
sentence = raw input('Input lowercase sentence:')
clientSocket.send(sentence)
modifiedSentence = clientSocket.recv(1024)
print 'From Server:', modifiedSentence
clientSocket.close()
```

```
TCP server
```

```
from socket import *
serverPort = 12000
serverSocket = socket(AF_INET, SOCK_STREAM)
serverSocket.bind(('', serverPort))
serverSocket.listen(1)
print 'The server is ready to receive'
while True:
    connectionSocket, clientAddress = serverSocket.accept()
    print "Connection form: ", clientAddress
    sentence = connectionSocket.recv(1024)
    capitalizedSentence = sentence.upper()
    connectionSocket.send(capitalizedSentence)
    connectionSocket.close()
```

TCP client persistent

```
from socket import *
serverName = 'localhost'
serverPort = 12000
clientSocket = socket(AF_INET, SOCK_STREAM)
clientSocket.connect((serverName, serverPort))
while True:
    sentence = raw_input('Input lowercase sentence ( . to stop):')
    clientSocket.send(sentence)
    if sentence == '.':
        break
    modifiedSentence = clientSocket.recv(1024)
    print 'From Server:', modifiedSentence
clientSocket.close()
```

TCP server persistent

```
from socket import *
serverPort = 12000
serverSocket = socket(AF INET, SOCK STREAM)
serverSocket.bind(('', serverPort))
serverSocket.listen(1)
while True:
    print 'The server is ready to receive'
    connectionSocket, clientAddress = serverSocket.accept()
    print "Connection form: ", clientAddress
    while True:
        sentence = connectionSocket.recv(1024)
        if sentence == '.':
           break
        capitalizedSentence = sentence.upper()
        connectionSocket.send(capitalizedSentence)
    connectionSocket.close()
```

TCP auto client

```
from socket import *
import time
serverName = 'localhost'
serverPort = 12000
```

```
clientSocket = socket(AF INET, SOCK STREAM)
clientSocket.connect((serverName, serverPort))
for a in range(100):
    clientSocket.send('A')
time.sleep(1)
clientSocket.send('.')
#clientSocket.recv(1024)
clientSocket.close()
TCP auto server
from socket import *
serverPort = 12000
serverSocket = socket(AF INET, SOCK STREAM)
serverSocket.bind(('', serverPort))
serverSocket.listen(1)
while True:
    print 'The server is ready to receive'
    connectionSocket, clientAddress = serverSocket.accept()
    print "Connection form: ", clientAddress
    while True:
        sentence = connectionSocket.recv(1024)
        if sentence == '.':
            break
        print len(sentence)
         connectionSocket.send(capitalizedSentence)
    connectionSocket.close()
TCP server thread
from socket import *
import thread
def handler(connectionSocket):
    while True:
        sentence = connectionSocket.recv(1024)
        if sentence == '.':
            break
        capitalizedSentence = sentence.upper()
        connectionSocket.send(capitalizedSentence)
    connectionSocket.close()
serverPort = 12000
serverSocket = socket(AF INET, SOCK STREAM)
serverSocket.setsockopt(SOL SOCKET, SO REUSEADDR, 1)
serverSocket.bind(('', serverPort))
serverSocket.listen(1)
while True:
    print 'The server is ready to receive'
    newSocket, addr = serverSocket.accept()
    thread.start new thread(handler, (newSocket,))
```