



root@savostinaav: ~ — -bash
alinochka@savostinaav:~$ [-d /sys/firmware/efi] && echo "UEFI" || echo "BIOS"
UEFI
alinochka@savostinaav:~$ su -
Password:
root@savostinaav:~# efibootmgr -v
BootCurrent: 0003
Timeout: 0 seconds
BootOrder: 0003,0000,0002
Boot0000* UiApp FvVol(7cb8bdc9-f8eb-4f34-aaea-3ee4af6516a1)/FvFile(462caa21-7614-4503-836e-8ab6f4662331)
dp: 04 07 14 00 c9 bd b8 7c eb f8 34 4f aa ea 3e e4 af 65 16 a1 / 04 06 14 00 21 aa 2c 46 14 76 03 45 83 6e 8a b6 f4 66 23 31 / 7f ff 04 00
Boot0002* UEFI VBOX HARDDISK VB8e23dff7-90f162c6 PciRoot(0x0)/Pci(0xd,0x0)/Sata(0,65535,0){auto_created_boot_option}
dp: 02 01 0c 00 d0 41 03 0a 00 00 00 00 / 01 01 06 00 00 0d / 03 12 0a 00 00 00 ff ff 00 00 / 7f ff 04 00
data: 4e ac 08 81 11 9f 59 4d 85 0e e2 1a 52 2c 59 b2
Boot0003* Ubuntu HD(1,GPT,15f3e503-af4d-421f-8b5b-b95c9f167eba,0x800,0x219800)/\EFI\ubuntu\shimx64.efi
dp: 04 01 2a 00 01 00 00 00 00 08 00 00 00 00 00 00 00 98 21 00 00 00 00 00 03 e5 f3 15 4d af 1f 42 8b 5b b9 5c 9f 16 7e ba 02 02 / 04 04 34 00 5c 00 45 00 46 00 49 00 5c 00 75 00 62 00 75 00 6e 00 74 00 75 00 5c 00 73 00 68 00 69 00 6d 00 78 00 36 00 34 00 2e 00 65 00 66 00 69 00 00 00 / 7f ff 04 00
root@savostinaav:~# mount | grep efi
efivarfs on /sys/firmware/efi/efivars type efivarfs (rw,nosuid,nodev,noexec,relatime)
/dev/sda1 on /boot/efi type vfat (rw,relatime,fmask=0022,dmask=0022,codepage=437,iocharset=iso8859-1,shortname=mixed,errors=remount-ro)
root@savostinaav:~# fdisk -l /dev/sda
Disk /dev/sda: 25 GiB, 26843545600 bytes, 52428800 sectors
Disk model: VBOX HARDDISK
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: gpt
Disk identifier: 465B3358-1863-494D-B982-426CF054059D
Device Start End Sectors Size Type
/dev/sda1 2048 2203647 2201600 1G EFI System
/dev/sda2 2203648 52426751 50223104 23.9G Linux filesystem
root@savostinaav:~# parted /dev/sda print | grep "Partition Table"
Partition Table: gpt
root@savostinaav:~# fdisk -l /dev/sda | grep -i bios
root@savostinaav:~#



root@savostinaav: ~ — -bash
root@savostinaav:~# cat /etc/default/grub
If you change this file or any /etc/default/grub.d/*.cfg file,
run 'update-grub' afterwards to update /boot/grub/grub.cfg.
For full documentation of the options in these files, see:
info -f grub -n 'Simple configuration'
GRUB_DEFAULT=0
GRUB_TIMEOUT_STYLE=menu
GRUB_TIMEOUT=10
GRUB_DISTRIBUTOR=`( . /etc/os-release && echo ${NAME} )`
GRUB_CMDLINE_LINUX_DEFAULT=""
GRUB_CMDLINE_LINUX=""
If your computer has multiple operating systems installed, then you
probably want to run os-prober. However, if your computer is a host
for guest OSes installed via LVM or raw disk devices, running
os-prober can cause damage to those guest OSes as it mounts
filesystems to look for things.
#GRUB_DISABLE_OS_PROBER=false
Uncomment to enable BadRAM filtering, modify to suit your needs
This works with Linux (no patch required) and with any kernel that obtains
the memory map information from GRUB (GNU Mach, kernel of FreeBSD ...)
#GRUB_BADRAM="0x01234567,0xfefefefe,0x89abcdef,0xefefefef"
Uncomment to disable graphical terminal
#GRUB_TERMINAL=console
The resolution used on graphical terminal
note that you can use only modes which your graphic card supports via VBE/GOP/UGA
you can see them in real GRUB with the command 'videoinfo'
#GRUB_GFXMODE=640x480
Uncomment if you don't want GRUB to pass "root=UUID=xxx" parameter to Linux
#GRUB_DISABLE_LINUX_UUID=true
Uncomment to disable generation of recovery mode menu entries
#GRUB_DISABLE_RECOVERY="true"


```
root@savostinaav: ~ — -bash


# Uncomment to get a beep at grub start
#GRUB_INIT_TUNE="480 440 1"
root@savostinaav:~# ls -1 /etc/grub.d/
00_header
05_debian_theme
10_linux
10_linux_zfs
20_linux_xen
20_memtest86+
30_os-prober
30_uefi-firmware
35_fwupd
40_custom
41_custom
README
root@savostinaav:~# cat /etc/grub.d/40_custom
#!/bin/sh
exec tail -n +3 $0
# This file provides an easy way to add custom menu entries.  Simply type the
# menu entries you want to add after this comment.  Be careful not to change
# the 'exec tail' line above.
root@savostinaav:~# grep -A5 "menuentry 'ALT" /boot/grub/grub.cfg | head -20
root@savostinaav:~# blkid
/dev/loop1: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop8: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop6: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop4: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop11: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop2: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop0: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop9: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop7: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/sda2: UUID="e1314306-5a62-412a-8548-2d91fb9e234b" BLOCK_SIZE="4096" TYPE="ext4" PARTUUID="b5cc4109-de01-4cbd-9248-4ac319fc3077"
/dev/sda1: UUID="7E02-97B8" BLOCK_SIZE="512" TYPE="vfat" PARTUUID="15f3e503-af4d-421f-8b5b-b95c9f167eba"
/dev/loop5: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop12: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop3: BLOCK_SIZE="131072" TYPE="squashfs"
/dev/loop10: BLOCK_SIZE="131072" TYPE="squashfs"
root@savostinaav:~#
```


```
/dev/loop10: BLOCK_SIZE="131072" TYPE="squashfs"
root@savostinaav:~# grep "GRUB_CMDLINE_LINUX" /etc/default/grub
GRUB_CMDLINE_LINUX_DEFAULT=""
GRUB_CMDLINE_LINUX=""
root@savostinaav:~# grep OS_PROBER /etc/default/grub
#GRUB_DISABLE_OS_PROBER=false
root@savostinaav:~#
```





[OK] Started systemd-ask-password-console.path - Dispatch Password Requests
[OK] Reached target cryptsetup.target - Local Encrypted Volumes.
[OK] Found device dev-disk-by\x2duuid-7E02\x2d97B8.device - VBOX_HARDDISK 1.
Starting systemd-fsck@dev-disk-by\x2duuid-7E02\x2d97B8.service - File S
[OK] Finished systemd-fsck@dev-disk-by\x2duuid-7E02\x2d97B8.service - File S
Mounting boot-efi.mount - /boot/efi...
[OK] Mounted boot-efi.mount - /boot/efi.
[OK] Reached target local-fs.target - Local File Systems.
Starting apparmor.service - Load AppArmor profiles...
Starting netplan-configure.service - Netplan Backend Configuration...
Starting plymouth-read-write.service - Tell Plymouth To Write Out Runti
Starting systemd-binfmt.service - Set Up Additional Binary Formats...
Starting systemd-tmpfiles-setup.service - Create System Files and Direc
[OK] Finished plymouth-read-write.service - Tell Plymouth To Write Out Runti
Mounting proc-sys-fs-binfmt_misc.mount - Arbitrary Executable File Form
[OK] Mounted proc-sys-fs-binfmt_misc.mount - Arbitrary Executable File Forma
[OK] Finished systemd-binfmt.service - Set Up Additional Binary Formats.
[OK] Finished systemd-tmpfiles-setup.service - Create System Files and Direc
[5.151276] vmwgfx 0000:00:02.0: [drm] *ERROR* vmwgfx seems to be running on
an unsupported hypervisor.
[5.151286] vmwgfx 0000:00:02.0: [drm] *ERROR* This configuration is likely b
roken.
[5.151292] vmwgfx 0000:00:02.0: [drm] *ERROR* Please switch to a supported g
raphics device to avoid problems.
[OK] Finished netplan-configure.service - Netplan Backend Configuration.
[OK] Listening on systemd-rfkill.socket - Load/Save RF Kill Switch Status /dev/rfkill Watch.
[OK] Finished apparmor.service - Load AppArmor profiles.
[OK] Reached target sysinit.target - System Initialization.
Starting dracut-shutdown.service - Restore /run/initramfs on shutdown...
Starting grub-initrd-fallback.service - GRUB failed boot detection...
[OK] Started rescue.service - Rescue Shell.
[OK] Finished dracut-shutdown.service - Restore /run/initramfs on shutdown.
[OK] Finished grub-initrd-fallback.service - GRUB failed boot detection.
[OK] Reached target rescue.target - Rescue Mode.
You are in rescue mode. After logging in, type "journalctl -xb" to view
system logs, "systemctl reboot" to reboot, or "exit"
to continue bootup.
Enter root password for system maintenance
(or press Control-D to continue): _



GNU GRUB version 2.14
Minimal BASH-like line editing is supported. For the first word, TAB lists possible command completions. Anywhere
else TAB lists possible device or file completions. To enable less(1)-like paging, "set pager=1". ESC at any time
exits.
grub> ls
(memdisk) (proc) (hd0) (hd0,gpt2) (hd0,gpt1) (cd0)
grub> _



error: disk `hd0,msdos2' not found.
grub> cat (hd0,msdos2)/etc/os-release
error: disk `hd0,msdos2' not found.
grub> cat (hd0,msdos)/etc/os-release
error: disk `hd0,msdos' not found.
grub> cat (hd0,gpt2)/etc/os-release
PRETTY_NAME="Ubuntu 26.04.1 LTS"
NAME="Ubuntu"
VERSION_ID="26.04"
VERSION="26.04.1 LTS (Resolute Raccoon)"
VERSION_CODENAME=resolute
ID=ubuntu
ID_LIKE=debian
HOME_URL="https://www.ubuntu.com/"
SUPPORT_URL="https://help.ubuntu.com/"
BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-policy"
UBUNTU_CODENAME=resolute
LOGO=ubuntu-logo
grub> _
Поиск



System.map-7.0.0-43-generic initrd.img-7.0.0-43-generic
grub> cat (hd0,msdos2) /etc/system-release
error: filename expected.
grub> cat(hd0,msdos2) /etc/system-release
error: can't find command `cat(hd0,msdos2)'.
grub> cat(hd0,msdos2)/etc/system-release
error: can't find command `cat(hd0,msdos2)/etc/'.
grub> cat (hd0,msdos2)/etc/system-release
error: disk `hd0,msdos2' not found.
grub> cat (hd0,msdos2)/etc/os-release
error: disk `hd0,msdos2' not found.
grub> cat (hd0,msdos)/etc/os-release
error: disk `hd0,msdos' not found.
grub> cat (hd0,gpt2)/etc/os-release
PRETTY_NAME="Ubuntu 26.04.1 LTS"
NAME="Ubuntu"
VERSION_ID="26.04"
VERSION="26.04.1 LTS (Resolute Raccoon)"
VERSION_CODENAME=resolute
ID=ubuntu
ID_LIKE=debian
HOME_URL="https://www.ubuntu.com/"
SUPPORT_URL="https://help.ubuntu.com/"
BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-policy"
UBUNTU_CODENAME=resolute
LOGO=ubuntu-logo
grub> search --file --set=root /boot/vmlinuz-*
grub> linux /boot/vmlinuz-* root=UUID=
grub> ls -l
Device memdisk: Filesystem type squash4 - Last modification time 2025-08-12 14:29:16 Tuesday - Sector size 512B - Total size 824KiB
Device proc: Filesystem type procfs - Sector size 512B - Total size 0KiB
Device hd0: No known filesystem detected - Sector size 512B - Total size 26214400KiB
Partition hd0,gpt2: Filesystem type ext* - Last modification time 2026-11-10 19:25:49 Tuesday, UUID e1314306-5a62-412a-8548-2d91fb9e234b - Partition start at 1101824KiB - Total size 25111552KiB
Partition hd0,gpt1: Filesystem type fat, UUID 7E02-9788 - Partition start at 1024KiB - Total size 1100800KiB
Device cd0: No known filesystem detected - Sector size 2048B - Total size 2KiB
grub> linux /boot/vmlinuz-* root=UUID=<e1314306-5a62-412a-8548-2d91fb9e234b> ro quiet
error: syntax error.
error: incorrect command.
error: syntax error.
grub> linux /boot/vmlinuz-* root=UUID=e1314306-5a62-412a-8548-2d91fb9e234b ro quiet
grub> _
Автозахват клавиатуры
Поиск
ENG
11.11.2026






```
root@savostinaav: ~ — -bash
Found memtest86+ 64bit EFI image: /boot/mt86+x64
Found memtest86+ 32bit EFI image: /boot/mt86+ia32
Found memtest86+ 64bit image: /boot/mt86+x64
Found memtest86+ 32bit image: /boot/mt86+ia32
Warning: os-prober will not be executed to detect other bootable partitions.
Systems on them will not be added to the GRUB boot configuration.
Check GRUB_DISABLE_OS_PROBER documentation entry.
Adding boot menu entry for UEFI Firmware Settings ...
done
alinochka@savostinaav:~$ grub-mkconfig -o /boot/grub/grub.cfg
grub-mkconfig: You must run this as root
alinochka@savostinaav:~$ su -
Password:
root@savostinaav:~# grub-mkconfig -o /boot/grub/grub.cfg
Sourcing file `/etc/default/grub'
Sourcing file `/etc/default/grub.d/kdump-tools.cfg'
Generating grub configuration file ...
Found linux image: /boot/vmlinuz-7.0.0-43-generic
Found initrd image: /boot/initrd.img-7.0.0-43-generic
Found linux image: /boot/vmlinuz-7.0.0-30-generic
Found initrd image: /boot/initrd.img-7.0.0-30-generic
Found memtest86+ 64bit EFI image: /boot/mt86+x64
Found memtest86+ 32bit EFI image: /boot/mt86+ia32
Found memtest86+ 64bit image: /boot/mt86+x64
Found memtest86+ 32bit image: /boot/mt86+ia32
Warning: os-prober will not be executed to detect other bootable partitions.
Systems on them will not be added to the GRUB boot configuration.
Check GRUB_DISABLE_OS_PROBER documentation entry.
Adding boot menu entry for UEFI Firmware Settings ...
done
root@savostinaav:~# dd if=/dev/sda bs=512 count=1 2>/dev/null | hexdump -C | tail
00000000  00 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |................|
*
000001c0  02 00 ee ff ff ff 01 00  00 00 ff ff 1f 03 00 00  |................|
000001d0  00 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |................|
*
000001f0  00 00 00 00 00 00 00 00  00 00 00 00 00 00 55 aa  |..............U.|
00000200
root@savostinaav:~#
```



root@savostinaav: ~ — systemctl list-units --type=target --all
00000200
root@savostinaav:~# grub-install --target=x86_64-efi --efi- directory=/boot/efi --bootloader-id=ALT
Installing for x86_64-efi platform.
grub-install: error: failed to get canonical path of `directory=/boot/efi'.
root@savostinaav:~# grub-install --target=x86_64-efi --efi-directory=/boot/efi --bootloader-id=ALT
Installing for x86_64-efi platform.
Installation finished. No error reported.
root@savostinaav:~# efibootmgr -v | grep ALT
Boot0003* Ubuntu HD(1,GPT,15f3e503-af4d-421f-8b5b-b95c9f167eba,0x800,0x219800)/\EFI\ALT\shimx64.efi
root@savostinaav:~# ps -p 1 # -p pid процесса -o
PID TTY TIME CMD
1 ? 00:00:02 systemd
root@savostinaav:~# systemctl list-units --type=target --all
UNIT LOAD ACTIVE SUB DESCRIPTION
basic.target loaded active active Basic System
blockdev@dev-disk-by\x2duuid-7E02\x2d97B8.target loaded inactive dead Block Device Preparation for /dev/di
blockdev@dev-disk-by\x2duuid-e1314306\x2d5a62\x2d412a\x2d8548\x2d2d91fb9e234b.target loaded inactive dead Block Device Preparation for /dev/di
blockdev@dev-loop0.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop1.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop10.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop11.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop12.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop13.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop14.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop15.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop2.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop3.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop4.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop5.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop6.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop7.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop8.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-loop9.target loaded inactive dead Block Device Preparation for /dev/lo
blockdev@dev-sda1.target loaded inactive dead Block Device Preparation for /dev/sd
boot-complete.target loaded active active Boot Completion Check
cloud-config.target loaded inactive dead Cloud-config availability
cloud-init.target loaded inactive dead Cloud-init target
cryptsetup-pre.target loaded inactive dead Local Encrypted Volumes (Pre)
cryptsetup.target loaded active active Local Encrypted Volumes



Ubuntu 26.04.1 LTS savostinaav tty1
savostinaav login: alinochka
Password:
Welcome to Ubuntu 26.04.1 LTS (GNU/Linux 7.0.0-43-generic x86_64)
* Documentation: https://docs.ubuntu.com
* Management: https://landscape.canonical.com
* Support: https://ubuntu.com/pro
Expanded Security Maintenance for Applications is not enabled.
111 updates can be applied immediately.
13 of these updates are standard security updates.
To see these additional updates run: apt list --upgradable
Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status
The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.
alinochka@savostinaav:~$ _


Ubuntu 26.04.1 LTS savostinaav tty3
savostinaav login: alinochka
Password:
Welcome to Ubuntu 26.04.1 LTS (GNU/Linux 7.0.0-43-generic x86_64)
* Documentation: https://docs.ubuntu.com
* Management: https://landscape.canonical.com
* Support: https://ubuntu.com/pro
Expanded Security Maintenance for Applications is not enabled.
111 updates can be applied immediately.
13 of these updates are standard security updates.
To see these additional updates run: apt list --upgradable
Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status
alinochka@savostinaav:~$ systemctl set-defailt graphical.target
Unknown command verb 'set-defailt', did you mean 'set-default'?
alinochka@savostinaav:~$ systemctl set-default graphical.target
==== AUTHENTICATING FOR org.freedesktop.systemd1.manage-unit-files ====
Authentication is required to manage system service or unit files.
Authenticating as: alinochka
Password:
==== AUTHENTICATION COMPLETE ====
Created symlink '/etc/systemd/system/default.target' → '/usr/lib/systemd/system/graphical.target'.
alinochka@savostinaav:~$ reboot


root@savostinaav: ~ — systemctl list-dependencies graphical.target
alinochka@savostinaav:~$ su -
Password:
root@savostinaav:~# systemd-analyze blame | head -10
8.584s dev-rfkill.device
8.584s sys-devices-virtual-misc-rfkill.device
7.323s dev-disk-by\x2dpath-pci\x2d0000:00:01.1\x2data\x2d1.0.device
7.323s dev-cdrom.device
7.323s dev-sr0.device
7.323s sys-devices-pci0000:00-0000:00:01.1-ata1-host0-target0:0:0-0:0:0:0-block-sr0.device
7.323s dev-disk-by\x2ddiskseq-10.device
7.323s dev-disk-by\x2dpath-pci\x2d0000:00:01.1\x2data\x2d1.device
7.323s dev-disk-by\x2did-ata\x2dVBOX_CD\x2dROM_VB0\x2d01f003f6.device
6.976s dev-ttyS3.device
root@savostinaav:~# systemctl list-dependencies graphical.target
graphical.target
● ├─accounts-daemon.service
● ├─gdm.service
● ├─power-profiles-daemon.service
● ├─switcheroo-control.service
● ├─udisks2.service
● └─multi-user.target
○ ├─anacron.service
● ├─apport.service
● ├─avahi-daemon.service
● ├─chrony.service
● ├─console-setup.service
● ├─cron.service
● ├─cups-browsed.service
● ├─cups.path
● ├─cups.service
● ├─dbus.service
○ ├─dmesg.service
○ ├─e2scrub_reap.service
○ ├─grub-initrd-fallback.service
○ ├─grub2-common.service
● ├─ModemManager.service
● ├─networkd-dispatcher.service
● ├─NetworkManager.service
● ├─openvpn.service
● ├─plymouth-quit-wait.service


root@savostinaav: ~ — -bash
├─apt-daily.timer
├─dpkg-db-backup.timer
├─e2scrub_all.timer
├─fstrim.timer
├─fwupd-refresh.timer
├─logrotate.timer
├─man-db.timer
├─motd-news.timer
├─snapd.snap-repair.timer
├─systemd-tmpfiles-clean.timer
├─ua-timer.timer
├─update-notifier-download.timer
└─update-notifier-motd.timer
├─getty.target
├─getty-static.service
└─getty@tty1.service
└─remote-fs.target
root@savostinaav:~# systemctl list-units --state=running --type=service | head -20
UNIT LOAD ACTIVE SUB DESCRIPTION
accounts-daemon.service loaded active running Accounts Service
avahi-daemon.service loaded active running Avahi mDNS/DNS-SD Stack
chrony.service loaded active running chrony, an NTP client/server
colord.service loaded active running Manage, Install and Generate Color Profiles
cron.service loaded active running Regular background program processing daemon
cups-browsed.service loaded active running Make remote CUPS printers available locally
cups.service loaded active running CUPS Scheduler
dbus.service loaded active running D-Bus System Message Bus
gdm.service loaded active running GNOME Display Manager
ModemManager.service loaded active running Modem Manager
networkd-dispatcher.service loaded active running Dispatcher daemon for systemd-networkd
NetworkManager.service loaded active running Network Manager
polkit.service loaded active running Authorization Manager
power-profiles-daemon.service loaded active running Power Profiles daemon
rsyslog.service loaded active running System Logging Service
rtkit-daemon.service loaded active running RealtimeKit Scheduling Policy Service
snapd.service loaded active running Snap Daemon
switcheroo-control.service loaded active running Switcheroo Control Proxy service
systemd-journald.service loaded active running Journal Service
root@savostinaav:~#


root@savostinaav: ~ — -bash
root@savostinaav:~# systemctl get-default >> boot_report.txt
root@savostinaav:~# systemctl list-units --state=running --type=service | head -20 >> boot_report.txt
root@savostinaav:~# cat boot_report.txt
GRUB_CMDLINE_LINUX_DEFAULT=""
GRUB_CMDLINE_LINUX=""
/boot/vmlinuz-7.0.0-30-generic
/boot/vmlinuz-7.0.0-43-generic
Module Size Used by
snd_seq_dummy 12288 0
snd_hrtimer 12288 1
qrtr 53248 2
intel_rapl_msr 20480 0
snd_intel8x0 57344 1
snd_ac97_codec 200704 1 snd_intel8x0
ac97_bus 12288 1 snd_ac97_codec
intel_rapl_common 57344 1 intel_rapl_msr
snd_pcm 212992 2 snd_intel8x0,snd_ac97_codec
snd_seq_midi 24576 0
snd_seq_midi_event 16384 1 snd_seq_midi
snd_rawmidi 57344 1 snd_seq_midi
binfmt_misc 24576 1
snd_seq 126976 9 snd_seq_midi,snd_seq_midi_event,snd_seq_dummy
nls_iso8859_1 12288 1
snd_seq_device 16384 3 snd_seq,snd_seq_midi,snd_rawmidi
snd_timer 53248 3 snd_seq,snd_hrtimer,snd_pcm
snd 147456 11 snd_seq,snd_seq_device,snd_intel8x0,snd_timer,snd_ac97_codec,snd_pcm,snd_rawmidi
vmwgfx 479232 2
i2c_piix4 36864 0
drm_ttm_helper 20480 2 vmwgfx
e1000 188416 0
soundcore 16384 1 snd
i2c_smbus 20480 1 i2c_piix4
vboxguest 57344 0
ttm 139264 2 vmwgfx,drm_ttm_helper
joydev 32768 0
input_leds 12288 0
mac_hid 12288 0
sch_fq_codel 28672 2
efi_pstore 12288 0
hid_generic 12288 0


root@savostinaav: ~ — -bash
usbhid 86016 0
hid 286720 2 usbhid,hid_generic
ghash_clmulni_intel 12288 0
ahci 57344 2
psmouse 225280 0
libahci 57344 1 ahci
video 77824 0
wmi 36864 1 video
serio_raw 20480 0
pata_acpi 12288 0
msr 12288 0
ppdev 24576 0
lp 32768 0
parport 81920 2 lp,ppdev
dmi_sysfs 28672 0
autofs4 61440 2
aesni_intel 98304 0
graphical.target
UNIT LOAD ACTIVE SUB DESCRIPTION
accounts-daemon.service loaded active running Accounts Service
avahi-daemon.service loaded active running Avahi mDNS/DNS-SD Stack
chrony.service loaded active running chrony, an NTP client/server
colord.service loaded active running Manage, Install and Generate Color Profiles
cron.service loaded active running Regular background program processing daemon
cups-browsed.service loaded active running Make remote CUPS printers available locally
cups.service loaded active running CUPS Scheduler
dbus.service loaded active running D-Bus System Message Bus
gdm.service loaded active running GNOME Display Manager
ModemManager.service loaded active running Modem Manager
networkd-dispatcher.service loaded active running Dispatcher daemon for systemd-networkd
NetworkManager.service loaded active running Network Manager
polkit.service loaded active running Authorization Manager
power-profiles-daemon.service loaded active running Power Profiles daemon
rsyslog.service loaded active running System Logging Service
rtkit-daemon.service loaded active running RealtimeKit Scheduling Policy Service
snapd.service loaded active running Snap Daemon
switcheroo-control.service loaded active running Switcheroo Control Proxy service
systemd-journald.service loaded active running Journal Service
root@savostinaav:~#