

Ejercicio 1

Partial Routers 00189021 - GNS3

File Edit View Control Node Annotate Tools Help

End devices

- ATM switch
- c7200
- Cisco 7200 124-24T5
- Cloud
- Ethernet hub
- Ethernet switch
- Frame Relay switch
- NAT
- VPCS

+ New template

Console

Error while creating link: Connecting a ethernet interface to a router. It is not possible to connect a ethernet interface to a router.

changed state to down
R1-00189021(config)#
*Jun 5 08:40:19.651: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R1-00189021(config)#
R1-00189021(config)#ip route 10.18.90.0 255.255.255.192 10.18.90.3
%Invalid next hop address (it's this router)
R1-00189021(config)#ip route 10.18.90.0 255.255.255.252 10.18.90.121
%Invalid next hop address (it's this router)
R1-00189021(config)#ip route 10.18.90.124 255.255.255.252 10.18.90.122
R1-00189021(config)#ip route 10.18.90.112 255.255.255.248 10.18.90.115
R1-00189021(config)#end
R1-00189021#wri
*Jun 5 08:50:47.519: %SYS-5-CONFIG_I: Configured from console by console
R1-00189021#write memory
Building configuration...
[OK]
R1-00189021#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.18.90.3	YES	manual	up	up
FastEthernet1/0	10.18.90.67	YES	manual	up	up
FastEthernet2/0	10.18.90.99	YES	manual	up	up
Serial3/0	10.18.90.121	YES	manual	up	up
Serial3/1	unassigned	YES	unset	administratively down	down
Serial3/2	unassigned	YES	unset	administratively down	down
Serial3/3	unassigned	YES	unset	administratively down	down

Topology Summary

Node Console

- PC1 telnet localhost:5000
- PC2 telnet localhost:5002
- PC3 telnet localhost:5004
- PC4 telnet localhost:5006
- R1 telnet localhost:5008
- R2 telnet localhost:5007
- R3 telnet localhost:5008

Servers Summary

- AP CPU 23.9%, RAM 55.7%

solarwinds Solar-PuTTY free tool

© 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

1 error

R1 R2 R3

*Jun 5 08:37:33.755: %LINK-3-UPDOWN: Interface Serial2/0, changed state to up
R2-00189021(config)#
*Jun 5 08:37:34.759: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
R2-00189021(config)#interface S2/1
R2-00189021(config-if)#ip address 10.18.90.125 255.255.255.252
R2-00189021(config-if)#no shutdown
R2-00189021(config-if)#exit
*Jun 5 08:38:16.887: %LINK-3-UPDOWN: Interface Serial2/1, changed state to up
R2-00189021(config-if)#exit
R2-00189021(config)#
*Jun 5 08:38:17.891: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/1, changed state to up
R2-00189021(config)#
*Jun 5 08:38:39.355: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/1, changed state to down
R2-00189021(config)#
*Jun 5 08:41:29.355: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/1, changed state to up
R2-00189021(config)#
R2-00189021(config)#ip route 10.18.90.0 255.255.255.192 10.18.90.121
R2-00189021(config)#ip route 10.18.90.64 255.255.255.224 10.18.90.121
R2-00189021(config)#ip route 10.18.90.96 255.255.255.240 10.18.90.121
R2-00189021(config)#ip route 10.18.90.112 255.255.255.248 10.18.90.126
R2-00189021(config)#end
R2-00189021#wri
*Jun 5 08:53:02.027: %SYS-5-CONFIG_I: Configured from console by console
R2-00189021#write memory
Building configuration...
[OK]
R2-00189021#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet1/0	unassigned	YES	unset	administratively down	down
Serial2/0	10.18.90.122	YES	manual	up	up
Serial2/1	10.18.90.125	YES	manual	up	up
Serial2/2	unassigned	YES	unset	administratively down	down
Serial2/3	unassigned	YES	unset	administratively down	down

R2-00189021#

```
R3
R1
R2
R3
R3(config)#hostname R3-00189021
R3-00189021(config)#interface F0/0
R3-00189021(config-if)#ip address 10.18.90.115 255.255.255.248
R3-00189021(config-if)#no shutdown
R3-00189021(config-if)#exit
*Jun  5 08:39:40.155: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Jun  5 08:39:41.155: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
R3-00189021(config-if)#exit
R3-00189021(config)#interface s2/0
R3-00189021(config-if)#ip address 10.18.90.126 255.255.255.252
R3-00189021(config-if)#no shutdown
R3-00189021(config-if)#exit
*Jun  5 08:40:38.771: %LINK-3-UPDOWN: Interface Serial2/0, changed state to up
R3-00189021(config-if)#exit
*Jun  5 08:40:39.775: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
R3-00189021(config-if)#exit
R3-00189021(config)#
R3-00189021(config)#ip route 10.18.90.120 255.255.255.252 10.18.90.125
R3-00189021(config)#ip route 10.18.90.0 255.255.255.192 10.18.90.122
R3-00189021(config)#ip route 10.18.90.64 255.255.255.224 10.18.90.122
R3-00189021(config)#ip route 10.18.90.96 255.255.255.248 10.18.90.122
R3-00189021(config)#end
R3-00189021#w
*Jun  5 08:55:27.315: %SYS-5-CONFIG_I: Configured from console by console
R3-00189021#write memory
Building configuration...
[OK]
R3-00189021#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.18.90.115    YES manual up          up
FastEthernet1/0 unassigned      YES unset  administratively down down
Serial2/0       10.18.90.126    YES manual up          up
Serial2/1       unassigned      YES unset  administratively down down
Serial2/2       unassigned      YES unset  administratively down down
Serial2/3       unassigned      YES unset  administratively down down
R3-00189021#
```

```
R1-00189021#write memory
Building configuration...
[OK]
R1-00189021#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.18.90.3      YES manual up          up
FastEthernet1/0 10.18.90.67     YES manual up          up
FastEthernet2/0 10.18.90.99     YES manual up          up
Serial3/0       10.18.90.121    YES manual up          up
Serial3/1       unassigned      YES unset  administratively down down
Serial3/2       unassigned      YES unset  administratively down down
Serial3/3       unassigned      YES unset  administratively down down
R1-00189021#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.18.90.3      YES manual up          up
FastEthernet1/0 10.18.90.67     YES manual up          up
FastEthernet2/0 10.18.90.99     YES manual up          up
Serial3/0       10.18.90.121    YES manual up          up
Serial3/1       unassigned      YES unset  administratively down down
Serial3/2       unassigned      YES unset  administratively down down
Serial3/3       unassigned      YES unset  administratively down down
R1-00189021#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

 10.0.0.0/8 is variably subnetted, 5 subnets, 4 masks
C    10.18.90.64/27 is directly connected, FastEthernet1/0
C    10.18.90.96/28 is directly connected, FastEthernet2/0
C    10.18.90.120/30 is directly connected, Serial3/0
S    10.18.90.124/30 [1/0] via 10.18.90.122
C    10.18.90.0/26 is directly connected, FastEthernet0/0
R1-00189021#
```

solarwinds | Solar-PuTTY free tool | © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

```
changed state to up
R2-00189021(config)#
R2-00189021(config)#ip route 10.18.90.0 255.255.255.192 10.18.90.121
R2-00189021(config)#ip route 10.18.90.64 255.255.255.224 10.18.90.121
R2-00189021(config)#ip route 10.18.90.96 255.255.255.240 10.18.90.121
R2-00189021(config)#ip route 10.18.90.112 255.255.255.248 10.18.90.126
R2-00189021(config)#end
R2-00189021#wri
*Jun  5 08:53:02.027: %SYS-5-CONFIG_I: Configured from console by console
R2-00189021#write memory
Building configuration...
[OK]
R2-00189021#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    unassigned      YES unset    administratively down down
FastEthernet1/0    unassigned      YES unset    administratively down down
Serial2/0          10.18.90.122    YES manual   up          up
Serial2/1          10.18.90.125    YES manual   up          up
Serial2/2          unassigned      YES unset    administratively down down
Serial2/3          unassigned      YES unset    administratively down down
R2-00189021#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/8 is variably subnetted, 6 subnets, 5 masks
S       10.18.90.64/27 [1/0] via 10.18.90.121
S       10.18.90.96/28 [1/0] via 10.18.90.121
S       10.18.90.112/29 [1/0] via 10.18.90.126
C       10.18.90.120/30 is directly connected, Serial2/0
C       10.18.90.124/30 is directly connected, Serial2/1
S       10.18.90.0/26 [1/0] via 10.18.90.121
R2-00189021#
```

```
R1 R2 R3
R3-00189021(config-if)#exit
R3-00189021(config)#
R3-00189021(config)#ip route 10.18.90.120 255.255.255.252 10.18.90.125
R3-00189021(config)#ip route 10.18.90.0 255.255.255.192 10.18.90.122
R3-00189021(config)#ip route 10.18.90.64 255.255.255.224 10.18.90.122
R3-00189021(config)#ip route 10.18.90.96 255.255.255.248 10.18.90.122
R3-00189021(config)#end
R3-00189021#w
*Jun  5 08:55:27.315: %SYS-5-CONFIG_I: Configured from console by console
R3-00189021#write memory
Building configuration...
[OK]
R3-00189021#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    10.18.90.115    YES manual up          up
FastEthernet1/0    unassigned      YES unset   administratively down down
Serial2/0          10.18.90.126    YES manual up          up
Serial2/1          unassigned      YES unset   administratively down down
Serial2/2          unassigned      YES unset   administratively down down
Serial2/3          unassigned      YES unset   administratively down down
R3-00189021#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

    10.0.0.0/8 is variably subnetted, 6 subnets, 4 masks
S       10.18.90.64/27 [1/0] via 10.18.90.122
S       10.18.90.96/29 [1/0] via 10.18.90.122
C       10.18.90.112/29 is directly connected, FastEthernet0/0
S       10.18.90.120/30 [1/0] via 10.18.90.125
C       10.18.90.124/30 is directly connected, Serial2/0
S       10.18.90.0/26 [1/0] via 10.18.90.122
R3-00189021#
```

```
PC1> show ip
NAME      : PC1[1]
IP/MASK    : 10.18.90.1/26
GATEWAY    : 10.18.90.2
DNS        :
MAC        : 00:50:79:66:68:00
LPORT     : 10000
RHOST:PORT : 127.0.0.1:10001
MTU        : 1500
PC1> █
```

solarwinds | Solar-PuTTY *free tool* © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

erface to a ethernet interface is not allowed

```
PC2> show ip

NAME       : PC2[1]
IP/MASK     : 10.18.90.65/27
GATEWAY     : 10.18.90.66
DNS         :
MAC         : 00:50:79:66:68:01
LPORT      : 10002
RHOST:PORT  : 127.0.0.1:10003
MTU         : 1500

PC2> █
```

solarwinds | Solar-PuTTY *free tool* © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

Access to a ethernet interface is not allowed

```

Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

Checking for duplicate address...
PC1 : 10.18.90.97 255.255.255.240 gateway 10.18.90.98


PC3>
PC3> show ip

NAME       : PC3[1]
IP/MASK     : 10.18.90.97/28
GATEWAY     : 10.18.90.98
DNS         :
MAC         : 00:50:79:66:68:02
LPORT      : 10004
RHOST:PORT  : 127.0.0.1:10005
MTU         : 1500

PC3> █
```

solarwinds | Solar-PuTTY free tool

© 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.



The image shows a SolarWinds Solar-PuTTY terminal window with four tabs: PC2, PC1, PC4 (active), and PC3. The active tab PC4 displays the output of the 'show ip' command. The output lists network configuration details for PC4[1], including IP address, mask, gateway, DNS, MAC address, LPORT, RHOST:PORT, and MTU. The terminal interface is dark-themed with yellow text. At the bottom, the SolarWinds logo and 'Solar-PuTTY free tool' are visible on the left, and the copyright notice '© 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.' is on the right.

```
PC4> show ip

NAME       : PC4[1]
IP/MASK    : 10.18.90.113/28
GATEWAY    : 10.18.90.114
DNS        :
MAC        : 00:50:79:66:68:03
LPORT      : 10006
RHOST:PORT : 127.0.0.1:10007
MTU        : 1500

PC4>
```

solarwinds | Solar-PuTTY *free tool* © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

Ejercicio 2

```
R1-00189021(config)#interface f0/0
R1-00189021(config-if)#ip address 10.18.90.113 255.255.255.240
R1-00189021(config-if)#no shutdown
R1-00189021(config-if)#exit
R1-00189021(config)#interfa
*Jun  5 10:11:25.063: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Jun  5 10:11:26.063: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
R1-00189021(config)#interface s3/1
R1-00189021(config-if)#ip address 10.18.90.141 255.255.255.252
R1-00189021(config-if)#no shutdown
R1-00189021(config-if)#exit
R1-00189021(config)#
*Jun  5 10:12:19.243: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
R1-00189021(config)#
*Jun  5 10:12:20.247: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1, changed state to up
R1-00189021(config)#interface s3/0
R1-00189021(config-if)#ip address 10.18.90.137 255.255.255.252
R1-00189021(config-if)#no shutdown
R1-00189021(config-if)#exit
*Jun  5 10:13:46.091: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
R1-00189021(config-if)#exit
R1-00189021(config)#
*Jun  5 10:13:47.095: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R1-00189021(config)#exit
R1-00189021#s
*Jun  5 10:13:51.315: %SYS-5-CONFIG_I: Configured from console by console
R1-00189021#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
FastEthernet0/0          10.18.90.113    YES manual up          up
FastEthernet1/0          unassigned      YES unset  administratively down down
FastEthernet2/0          unassigned      YES unset  administratively down down
Serial3/0                 10.18.90.137    YES manual up          up
Serial3/1                 10.18.90.141    YES manual up          up
Serial3/2                 unassigned      YES unset  administratively down down
Serial3/3                 unassigned      YES unset  administratively down down
R1-00189021#
```

solarwinds | Solar-PuTTY free tool

© 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

```
R3 R2 R4 R5 R1
R5-00189021(config)#exit
R5-00189021#sh
*Jun  5 10:00:03.399: %SYS-5-CONFIG_I: Configured from console by console
R5-00189021#show ip interface brief
Interface          IP-Address      OK? Method Status      Prot
FastEthernet0/0    10.18.90.1     YES manual up          up
FastEthernet1/0    unassigned     YES unset  administratively down down
FastEthernet2/0    unassigned     YES unset  administratively down down
Serial3/0          10.18.90.158   YES manual up          down
Serial3/1          10.19.90.154   YES manual up          down
Serial3/2          unassigned     YES unset  administratively down down
Serial3/3          unassigned     YES unset  administratively down down
R5-00189021#
*Jun  5 10:01:02.583: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0,
changed state to up
R5-00189021#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    10.18.90.1     YES manual up          up
FastEthernet1/0    unassigned     YES unset  administratively down down
FastEthernet2/0    unassigned     YES unset  administratively down down
Serial3/0          10.18.90.158   YES manual up          up
Serial3/1          10.19.90.154   YES manual up          down
Serial3/2          unassigned     YES unset  administratively down down
Serial3/3          unassigned     YES unset  administratively down down
R5-00189021#
*Jun  5 10:12:12.847: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1, changed state to up
R5-00189021#
```

solarwinds | Solar-PuTTY free tool © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

```
solarwinds | Solar-PuTTY free tool | © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

R4-00189021(config-if)#ip address 10.18.90.150 255.255.255.252
R4-00189021(config-if)#no shutdown
R4-00189021(config-if)#exit
R4-00189021(config)#i
*Jun  5 10:03:16.323: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
R4-00189021(config)#interfa
*Jun  5 10:03:17.327: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R4-00189021(config)#interface s3/1
R4-00189021(config-if)#ip address 10.18.90.153 255.255.255.252
R4-00189021(config-if)#no shutdown
R4-00189021(config-if)#exit
R4-00189021(config)#
*Jun  5 10:04:40.751: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
R4-00189021(config)#
*Jun  5 10:04:41.755: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1, changed state to up
R4-00189021(config)#interface F0/0
R4-00189021(config-if)#ip address 10.18.90.129 255.255.255.248
R4-00189021(config-if)#no shutdown
R4-00189021(config-if)#exit
R4-00189021(config)#exit
R4-00189021#sho
*Jun  5 10:07:07.231: %SYS-5-CONFIG_I: Configured from console by console
R4-00189021#show interface brief
      ^
% Invalid input detected at '^' marker.

R4-00189021#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.18.90.129    YES manual up          up
FastEthernet1/0 unassigned      YES unset  administratively down down
FastEthernet2/0 unassigned      YES unset  administratively down down
Serial3/0       10.18.90.150    YES manual up          up
Serial3/1       10.18.90.153    YES manual up          up
Serial3/2       unassigned      YES unset  administratively down down
Serial3/3       unassigned      YES unset  administratively down down
R4-00189021#
```

```
R2-00189021(config-if)#exit
R2-00189021(config)#in
*Jun  5 09:55:58.555: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
R2-00189021(config)#inter
*Jun  5 09:55:59.559: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1,
changed state to up
R2-00189021(config)#interface s3/2
R2-00189021(config-if)#
*Jun  5 09:56:22.563: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1,
changed state to down
R2-00189021(config-if)#ip address 10.18.90.157 255.255.255.252
R2-00189021(config-if)#no shutdown
R2-00189021(config-if)#exit
R2-00189021(config)#
*Jun  5 09:58:25.667: %LINK-3-UPDOWN: Interface Serial3/2, changed state to up
R2-00189021(config)#
*Jun  5 09:58:26.671: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/2,
changed state to up
R2-00189021(config)#
R2-00189021(config)#exit
R2-00189021#sho
*Jun  5 10:02:03.307: %SYS-5-CONFIG_I: Configured from console by console
R2-00189021#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.18.90.65     YES manual up          up
FastEthernet1/0 unassigned      YES unset  administratively down down
FastEthernet2/0 unassigned      YES unset  administratively down down
Serial3/0       10.18.90.142    YES manual up          down
Serial3/1       10.18.90.146    YES manual up          down
Serial3/2       10.18.90.157    YES manual up          up
Serial3/3       unassigned      YES unset  administratively down down
R2-00189021#
*Jun  5 10:02:52.655: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/1, changed state to up
R2-00189021#
*Jun  5 10:20:43.063: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R2-00189021#
```

solarwinds | Solar-PuTTY free tool

© 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

```
R3-00189021(config-if)#ip address 10.18.90.149 255.255.255.252
R3-00189021(config-if)#no shutdown
R3-00189021(config-if)#exit
R3-00189021(config)#
*Jun  5 10:00:47.939: %LINK-3-UPDOWN: Interface Serial3/2, changed state to up
R3-00189021(config)#int
*Jun  5 10:00:48.943: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/2, changed state to up
R3-00189021(config)#interface s3/0
R3-00189021(config-if)#
*Jun  5 10:01:12.675: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/2, changed state to down
R3-00189021(config-if)#ip address 10.18.90.138 255.255.255.252
R3-00189021(config-if)#no shutdown
R3-00189021(config-if)#exit
R3-00189021(config)#
*Jun  5 10:01:50.847: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
R3-00189021(config)#
*Jun  5 10:01:51.851: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R3-00189021(config)#
*Jun  5 10:02:12.707: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to down
R3-00189021(config)#exit
R3-00189021#show
*Jun  5 10:04:45.455: %SYS-5-CONFIG_I: Configured from console by console
R3-00189021#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
FastEthernet0/0          10.18.90.97     YES manual up          up
FastEthernet1/0          unassigned      YES unset  administratively down down
FastEthernet2/0          unassigned      YES unset  administratively down down
Serial3/0                10.18.90.138    YES manual up          down
Serial3/1                10.18.90.145    YES manual up          up
Serial3/2                10.18.90.149    YES manual up          down
Serial3/3                unassigned      YES unset  administratively down down
R3-00189021#
*Jun  5 10:06:02.771: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/2, changed state to up
R3-00189021#
*Jun  5 10:19:43.067: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
R3-00189021#
```

solarwinds | Solar-PuTTY free tool © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

