

Techno Chatbot Live Chat

Desktop Browser Notification Setup & Setup Troubleshooting Guide

UNDERSTANDING DESKTOP NOTIFICATIONS

Desktop browser notifications alert support agents instantly when incoming visitor messages or live chat inquiries arrive—even when working in another tab or program.

To receive alerts, notifications must be enabled in **two places**: inside the **WordPress Plugin Settings** and within your **Desktop Web Browser permissions**.

Step 1: Enable Notifications inside WordPress

Before configuring browser settings, ensure the global switch in your WordPress admin dashboard is turned on:

1. Log in to your **WordPress Dashboard**.
2. In the left sidebar menu, click on **Techno Chatbot**, then select **Chats**.
3. At the top of the interface, ensure you are on the **Live Chat** tab.
4. Locate the **Browser Notification** setting at the top of the panel.
5. Click the toggle switch so it displays **Enabled** (Green). If it shows *Disabled*, click it once to switch state.

STEP 2: BROWSER-SPECIFIC SETUP (PART 1)

Google Chrome

DESKTOP

Allowing Notifications:

1. Open your site in Chrome and click the **Site Information / Lock icon** next to the URL in the address bar.
2. Toggle the **Notifications** switch to **On**.
3. If prompted, click **Reload** to apply settings.

Unblocking previously blocked site:

Click Lock icon → **Site settings** → Find **Notifications** → Change from *Block* to *Allow*.

Chrome Rule: Requires secure HTTPS connections. Notifications will not trigger on plain HTTP sites.

Microsoft Edge

DESKTOP

Allowing Notifications:

1. Click the **View site information (Lock icon)** on the left side of the address bar.
2. Click the dropdown next to **Permissions for this site**.
3. Set **Notifications** to **Allow**.

Unblocking previously blocked site:

Click Lock icon → **Permissions for this site** → Locate **Notifications** → Select **Allow**.

Edge Rule: Windows Focus Assist settings can suppress Edge popups into the Action Center silently.

STEP 2: BROWSER-SPECIFIC SETUP (PART 2)

Mozilla Firefox

DESKTOP

Allowing Notifications:

1. Click the **Padlock icon** next to the website address.
2. In the panel, check permissions for **Send Notifications**.
3. Select **Allow** or clear any blocked status.

Unblocking previously blocked site:

Click Lock icon → Remove *Blocked Temporarily* by clicking the **X** next to it, then refresh page.

Firefox Rule: Private Browsing mode automatically revokes notification permissions when the session closes.

Apple Safari

MACOS

Allowing Notifications:

1. Open Safari, click **Safari** in top menu bar → **Settings** (or *Preferences*).
2. Click the **Websites** tab, then select **Notifications** from left column.
3. Find your WordPress site domain and set option to **Allow**.

Unblocking previously blocked site:

In Safari Settings → Websites → Notifications, change site status from *Deny* to *Allow*.

Safari Rule: macOS system permissions must also grant notification access to Safari in System Settings.

Opera

DESKTOP

Allowing Notifications:

1. Click the **Badge/Lock icon** to the left of the URL bar.
2. Click **Site settings**.
3. Scroll down to **Notifications** and change dropdown to **Allow**.

Unblocking previously blocked site:

Lock icon → Site settings → Notifications → Choose **Allow**.

Opera Rule: Ensure Opera's built-in Battery Saver is not throttling background tab alerts.

Brave

DESKTOP

Allowing Notifications:

1. Click the **Tune/Sliders icon** (left of address bar).
2. Click **Site settings**.
3. Set **Notifications** permission to **Allow**.

Unblocking previously blocked site:

Tune icon → Site settings → Permissions → Change *Block* to *Allow*.

Brave Rule: Brave Shields rarely blocks notifications, but standard Chromium permission rules apply.

TROUBLESHOOTING COMMON NOTIFICATION ISSUES

Issue	Possible Cause	Solution
No alerts despite enabling browser permissions	OS Focus Assistant, Do Not Disturb, or Concentration mode enabled.	Turn off Do Not Disturb on macOS (Control Center) or Focus Assist on Windows 10/11 Settings.
Browser prompt never appeared	Site is unencrypted (HTTP) or global browser settings block all prompts.	Ensure your WordPress domain uses <code>https://</code> . Check browser global settings to allow permission prompts.
Chats sound/popup stops when switching tabs	Browser tab throttling or memory saver sleeping the WordPress admin.	Keep the Techno Chatbot tab active or pinned in your browser tab bar. disable Memory Saver for your admin domain.