ANTU LSS PRO

TRADINGVIEW ALERT SETUP GUIDE

Institutional Liquidity Sweep & Fair Value Gap Execution System | Pine Script v6

TradingView Alert Setup Guide

Comprehensive Alert Configuration Manual

Overview

This guide provides complete instructions for configuring real-time notifications for **ANTU LSS PRO** on the TradingView platform.

TradingView allows you to receive instant alerts across multiple channels:

- Mobile push notifications on your phone (iOS / Android)
- Desktop browser sound and visual popup dialogs
- Direct email notifications
- Webhook JSON payloads for external alert routing

Step 1: Add Indicator to Chart

Before creating an alert, ensure that **ANTU LSS PRO** is added to your active chart:

1. Open the chart for your chosen ticker and timeframe (e.g., NIFTY 5m).
2. Confirm the indicator name **"ANTU LSS PRO"** is visible in the top-left legend.
3. Confirm the settings (such as Session Filter, Swing Length, and R:R) are configured as desired.

Step 2: Click the Create Alert Icon

1. In the top horizontal toolbar of TradingView, locate and click the **Clock icon (Create Alert)**.

*(Alternative: Right-click anywhere on the chart canvas and select **"Add alert on..."** or press the keyboard shortcut `Alt + A`).*

2. The **Create Alert** configuration modal dialog will appear.

Step 3: Select ANTU LSS PRO as the Condition

1. At the top of the alert dialog, locate the primary **"Condition"** dropdown menu.
2. By default, it may display the ticker name (e.g., `NIFTY`). Click the dropdown.
3. Scroll or search and select **ANTU LSS PRO**.

Step 4: Choose Your Alert Type

Once ANTU LSS PRO is selected, a secondary condition dropdown appears. Choose the option matching your trading preference:

Option 1: Standard Visual / Audio Notifications

- **`ANTU LSS PRO Long`:** Triggers exclusively when a valid Bullish Sweep + FVG retest occurs.
- **`ANTU LSS PRO Short`:** Triggers exclusively when a valid Bearish Sweep + FVG retest occurs.
- **`ANTU LSS PRO Any`:** Triggers whenever either a Long or Short setup is confirmed.

Option 2: Dynamic JSON Payload (Advanced)

- Select **`Any alert() function call`**.
- This option activates the indicator's internal **`alert()`** engine, which automatically packages the exact calculated Entry, Stop-Loss, and Take-Profit values into a clean JSON string.

Step 5: Choose Alert Trigger Frequency

This step is critical to ensure zero repainting:


1. Under **"Trigger"** or **"Expiration / Frequency"**, locate the trigger options.
2. Select: **"Once Per Bar Close"** (or *Once per bar close* depending on your TradingView version).

> ***IMPORTANT NOTE: CRITICAL RULE:*** *NEVER select "Only Once" (which deactivates the alert forever after one signal) or "Once Per Minute" / "Every time" (which can trigger on incomplete candles). Choosing **"Once Per Bar Close"** guarantees that the candle has completed, the sweep and FVG retest are mathematically locked, and the signal cannot disappear.*

Step 6: Enable Your Notification Channels

Navigate to the **"Notifications"** tab in the alert dialog:

- [x] **Notify in app:** Sends an instant push notification to your phone via the TradingView mobile app.
- [x] **Show pop-up:** Displays an on-screen dialog box on your computer screen.
- [x] **Play sound:** Plays an audible sound alert (choose your preferred tone and duration).
- [x] **Send email:** Forwards the alert notice directly to your registered email address.
- [ ] **Webhook URL (Optional):** If you route alerts to a webhook listener, check this box and enter your endpoint URL.



Step 7: Configure the Alert Message

For Standard Conditions (`ANTU LSS PRO Long / Short / Any`):

You can keep the default message or enter your own custom text:

```
ANTU LSS PRO — Signal Alert on {{ticker}} ({{interval}})
```

For Dynamic Webhook / `Any alert() function call`:

Leave the message field set to **`{{strategy.order.alert_message}}`** or **`{{plot("0")}}`** / default alert text, because the Pine Script code automatically transmits this structured JSON payload:

```
{
  "action": "BUY",
  "signal": "LONG",
  "indicator": "ANTU LSS PRO",
  "ticker": "{{ticker}}",
  "exchange": "{{exchange}}",
  "interval": "{{interval}}",
  "entry": 24520.50,
  "sl": 24480.25,
  "tp": 24601.00
}
```

Step 8: Save and Test the Alert

1. Click the blue **"Create"** (or **"Save"**) button at the bottom of the modal.
2. Look at the right sidebar of TradingView and open the **Alerts Log** (clock icon).
3. Confirm that your newly created alert appears under the **Active Alerts** list.
4. When a new candle closes that fulfills all the ANTU LSS PRO entry criteria, TradingView will immediately trigger your notification across all selected channels.

Practical Alert Troubleshooting

Issue Encountered	Likely Cause	Solution
No alerts triggering during market hours	Market session filter is inactive or set to different hours.	Check `sessionIndia` in settings. For non-Indian markets, set to `"0000-2359"`.
Alert triggered, but price moved slightly	Normal behavior: alert triggers upon candle close, and the next candle opened with a minor gap.	Use limit orders at the dashed entry line rather than market orders.
TradingView says alert limit reached	Free TradingView accounts allow a limited number of active alerts simultaneously.	Delete old/unused alerts in your Alerts Manager tab.
Alert triggered multiple times on one candle	Trigger was mistakenly set to "Every time".	Edit the alert and ensure frequency is set to **"Once Per Bar Close"**.

You are now equipped with real-time, hands-free market notification capabilities.