ANTU LSS PRO

INSTALLATION GUIDE

Institutional Liquidity Sweep & Fair Value Gap Execution System | Pine Script v6

Installation Guide

Step-by-Step Technical Setup Walkthrough for TradingView

Overview

This guide provides clear, step-by-step instructions for installing and running the **ANTU LSS PRO** indicator on the TradingView platform. Installation takes approximately 2 to 3 minutes and requires no programming knowledge.

System Requirements:

- A free or paid account on [TradingView](https://www.tradingview.com).
- Any modern web browser (Chrome, Edge, Firefox, Safari) or the TradingView Desktop app.
- The `ANTU_LSS_PRO.pine` source code file included in your product package.

Step 1: Open TradingView

1. Open your web browser and navigate to **www.tradingview.com**.
2. Log into your TradingView account.
3. Open any chart (for example, NIFTY, BANKNIFTY, AAPL, EURUSD, or BTCUSD).

Step 2: (Important) Connect Your Broker via Trading Panel

TradingView's standalone free tier has restrictions on live order execution and high-speed data. To execute trades live directly from your TradingView chart without paying for expensive subscriptions, connect your broker through the built-in **Trading Panel**:

1. Look at the bottom edge of your TradingView screen to find the console tab bar:

*Stock Screener | Pine Editor | Strategy Tester | **Trading Panel***.

2. Click on the **"Trading Panel"** tab.
3. Select your broker from the supported broker list:

- **DHAN (Recommended for Indian Traders):** Official TradingView partner. Click **Connect**, scan the QR code via your Dhan mobile app, or enter your registered mobile number and OTP.
- **FYERS:** Official TradingView broker partner. Click **Connect** and authenticate with your Fyers credentials.
- **PAPER TRADING (TradingView):** If you are learning or wish to test the ANTU LSS PRO indicator risk-free with virtual capital, select **Paper Trading** and click **Connect**.

4. Once authenticated, your live broker account balance, open positions, and instant Buy/Sell buttons will activate directly on your TradingView chart.




FIGURE: TRADINGVIEW BROKER INTEGRATION VIA TRADING PANEL (DHAN / FYERS / PAPER TRADING)

Step 3: Open Pine Editor

1. In the same bottom console tab bar (right next to Trading Panel), click on the **"Pine Editor"** tab.
2. The code editor workspace will expand.

Step 4: Create a New Script

1. In the top-right toolbar of the Pine Editor panel, click the dropdown or three dots menu.
2. Select **"New indicator"** (or click *Create new*).
3. Select all default template code (`Ctrl+A` / `Cmd+A`) and delete it so the editor is blank.

Step 5: Paste ANTU_LSS_PRO.pine Code

1. Open `ANTU_LSS_PRO.pine` (located in the `01_Indicator` folder) in any text editor.
2. Select all code (`Ctrl+A`) and copy it (`Ctrl+C`).
3. Paste the code into the empty Pine Editor window (`Ctrl+V`).

Step 6: Save the Script

1. Click the **"Save"** button in the Pine Editor toolbar (or press `Ctrl+S`).
2. Type the script title: **ANTU LSS PRO** and click **Save**.

Step 7: Add Indicator to Chart

1. Click the **"Add to chart"** button on the Pine Editor toolbar.
2. The indicator will load on your chart along with the real-time statistics table.




FIGURE: STEP-BY-STEP PINE EDITOR INSTALLATION FLOWCHART

Step 8: Configure Critical Inputs & Tuning Parameters

1. Move your mouse over the indicator name **"ANTU LSS PRO"** in the top-left chart legend.
2. Click the **Gear icon (Settings)**.
3. The Settings dialog box opens with three primary groups: **Detection**, **Risk**, and **Stats**.




FIGURE: CRITICAL INPUT SETTINGS & STRATEGY PARAMETER TUNING

Detailed Breakdown: Why These Specific Settings are Crucial

Understanding each parameter allows you to fine-tune ANTU LSS PRO for high-speed scalping versus structural day trading:

1. DETECTION GROUP:

- **`Swing Length` (Default: 10 | Scalping Preset: 3):**

- **Why it matters:** Controls how many candles to the left and right are required to confirm a pivot high (BSL) or pivot low (SSL).
- **Setting to 3 (Fast Scalping):** Detects quick micro-pivot wick rejections rapidly. Perfect for 1-minute, 3-minute, and 5-minute intraday trading on volatile instruments like Nifty, Bank Nifty, and Crypto where market makers hunt quick liquidity clusters.
- **Setting to 10 (Trend Following):** Filters out minor chop and only tracks major structural swing points. Ideal for 15-minute, 1-hour, or 4-hour charts.
- `Max Liq Levels` **(Default: 5 | Extended Memory: 10):**
- **Why it matters:** Sets the maximum number of un-swept liquidity levels kept in active memory.
- **Setting to 10:** Allows the indicator to monitor deeper structural swing pools from earlier in the day or previous sessions, ensuring no historical liquidity level is forgotten during extended consolidations.

2. RISK GROUP:

- `SL ATR Buffer` **(Default: 0.5 | Sniper Preset: 0.1):**
- **Why it matters:** Controls the extra volatility margin added beyond the extreme wick of the sweep for the Stop Loss (`slP = sweepWick ± atr * atrMult`).
- **Setting to 0.1 (Sniper Risk):** Anchors the Stop Loss tightly just 10% of 14-ATR beyond the wick extreme. This minimizes your risk distance (`slDist`), allowing tighter stops and larger lot sizes while keeping account capital risk capped at 1%. Targets are achieved much faster!
- **Setting to 0.5 (Conservative Buffer):** Provides wider breathing room to protect against sudden exchange spread widenings and erratic spikes.
- `R:R Ratio` **(Default: 2.0):**
- **Why it matters:** Establishes the Take Profit distance relative to risk (`tpDist = slDist * 2.0`).
- **The Mathematical Edge:** A 1:2 Risk-to-Reward ratio guarantees profitability over a sample of trades even with an ordinary 35%–40% win rate. Never lower this below 1.5.
- `Expire setup after N bars` **(Default: 30 bars):**
- **Why it matters:** Freshness invalidation rule. If price sweeps a liquidity level and produces an FVG, but fails to retest the 50% midpoint within 30 candles, the setup automatically expires. This prevents entering stale, low-momentum setups.

3. STATS & VISUALS GROUP:

- `Stats: Last N Signals` **(Default: 20):**
- Evaluates the win rate %, total wins, losses, and active setups across the last 20 signals on the live on-chart dashboard.
- `Show setup markers` **(Checked):**
- Visually renders the teal **"SSL▲"** and red **"BSL▼"** labels above/below candles at the moment institutional sweeps occur.

Recommended Presets by Trading Style:

Parameter	Aggressive Scalper (1m–3m)	Balanced Day Trader (5m–15m)	Swing Trader (1h–4h)
Swing Length	**3**	**5 – 10**	**10 – 15**
Max Liq Levels	**10**	**5**	**5**
SL ATR Buffer	**0.1**	**0.3 – 0.5**	**0.5 – 1.0**
R:R Ratio	**2.0**	**2.0**	**2.0 – 2.5**
Expire Bars	**20 – 30**	**30**	**50**
Timeframe	1m, 3m	5m, 15m	1h, 4h

4. Click **OK** to apply any changes.

Step 9: Select Appropriate Market & Timeframe

1. Choose an asset with healthy volume and tight spreads (e.g., Nifty Index, Bank Nifty, major equities, liquid Forex pairs, or top crypto pairs).
2. Select your preferred timeframe:

- **Intraday Scalping/Day Trading:** 3-minute, 5-minute, or 15-minute chart.
- **Swing Trading:** 1-hour or 4-hour chart.

3. Ensure the session filter matches your market hours.

Step 10: Verify Signals on Chart

1. Look back across the recent chart history to confirm visual elements:

- **"SSL▲"** labels printed below swing lows swept by price.
- **"BSL▼"** labels printed above swing highs swept by price.
- **Dashed White Lines** marking entry points at Fair Value Gap midpoints.
- **Green boxes** indicating Take Profit targets.
- **Red boxes** indicating Stop Loss levels.
- **Top-Right Table** displaying active Bias, Win Rate %, Wins, Losses, and Open signals.

Step 11: Create TradingView Alerts

1. Click the **Clock icon (Create Alert)** on the top TradingView toolbar.
2. Under the **Condition** dropdown, select **ANTU LSS PRO**.
3. Choose your desired trigger condition:

- `ANTU LSS PRO Long`
- `ANTU LSS PRO Short`
- `ANTU LSS PRO Any`
- Or `Any alert() function call` for dynamic JSON messages with entry, SL, and TP values.

4. Set the trigger frequency to: **Once Per Bar Close**.
5. Select your notification preferences (Play sound, Send email, Mobile app notification).
6. Click **Create**.




FIGURE: CRITICAL INPUT SETTINGS & STRATEGY PARAMETER TUNING

Installation Complete!

Your ANTU LSS PRO system is now fully operational. Refer to the **Quick Start Guide** and **User Guide** for strategic execution instructions.