

CMakeLists.txt

```

1 # Generated Cmake Pico project file
2 #U13157006
3 cmake_minimum_required(VERSION 3.13)
4
5 set(CMAKE_C_STANDARD 11)
6 set(CMAKE_CXX_STANDARD 17)
7 set(CMAKE_EXPORT_COMPILE_COMMANDS ON)
8
9 # Initialise pico_sdk from installed location
10 # (note this can come from environment, CMake cache etc)
11
12 # == DO NOT EDIT THE FOLLOWING LINES for the Raspberry Pi Pico VS Code Extension to
13 # work ==
14 if(WIN32)
15     set(USERHOME $ENV{USERPROFILE})
16 else()
17     set(USERHOME $ENV{HOME})
18 endif()
19 set(sdkVersion 2.3.0)
20 set(toolchainVersion 13_2_Rel1)
21 set(picotoolVersion 2.3.0)
22 set(picoVscode ${USERHOME}/.pico-sdk/cmake/pico-vscode.cmake)
23 if (EXISTS ${picoVscode})
24     include(${picoVscode})
25 endif()
26 #
27 =====
28 set(PICO_BOARD pico CACHE STRING "Board type")
29
30 # Pull in Raspberry Pi Pico SDK (must be before project)
31 include(pico_sdk_import.cmake)
32
33 project(hello_usb C CXX ASM)
34
35 # Initialise the Raspberry Pi Pico SDK
36 pico_sdk_init()
37
38 # Add executable. Default name is the project name, version 0.1
39
40 if (TARGET tinyusb_device)
41     add_executable(hello_usb
42         #hello_usb.c
43         movaddsubshift.S
44     )
45
46     # pull in common dependencies
47     target_link_libraries(hello_usb pico_stdlib)
48
49     # enable usb output, disable uart output
50     pico_enable_stdio_usb(hello_usb 0)
51     pico_enable_stdio_uart(hello_usb 0)

```

```
51  
52     # create map/bin/hex/uf2 file etc.  
53     pico_add_extra_outputs(hello_usb)  
54  
55     # add url via pico_set_program_url  
56 elseif(PICO_ON_DEVICE)  
57     message("Skipping hello_usb because TinyUSB submodule is not initialized in the  
58     SDK")  
59 endif()
```