

ptx(1) — Linux manual page

[NAME](#) | [SYNOPSIS](#) | [DESCRIPTION](#) | [AUTHOR](#) | [REPORTING BUGS](#) | [COPYRIGHT](#) | [SEE ALSO](#) | [COLOPHON](#)

 PTX(1)

User Commands

PTX(1)

NAME [top](#)

ptx – produce a permuted index of file contents

SYNOPSIS [top](#)

```
ptx [OPTION]... [INPUT]...    (without -G)
ptx -G [OPTION]... [INPUT] [OUTPUT]
```

DESCRIPTION [top](#)

Output a permuted index, including context, of the words in the input files.

With no FILE, or when FILE is -, read standard input.

Mandatory arguments to long options are mandatory for short options too.

- A, --auto-reference
output automatically generated references
- G, --traditional
behave more like System V 'ptx'
- F, --flag-truncation=STRING
use STRING for flagging line truncations. The default is '/'
- M, --macro-name=STRING
macro name to use instead of 'xx'
- O, --format=roff
generate output as roff directives
- R, --right-side-refs
put references at right, not counted in -w
- S, --sentence-regexp=REGEXP

for end of lines or end of sentences

- T, --format=tex**
generate output as TeX directives
- W, --word-regexp=REGEXP**
use REGEXP to match each keyword
- b, --break-file=FILE**
word break characters in this FILE
- f, --ignore-case**
fold lower case to upper case for sorting
- g, --gap-size=NUMBER**
gap size in columns between output fields
- i, --ignore-file=FILE**
read ignore word list from FILE
- o, --only-file=FILE**
read only word list from this FILE
- r, --references**
first field of each line is a reference
- t, --typeset-mode**
change the default width from 72 to 100
- w, --width=NUMBER**
output width in columns, reference excluded
- help** display this help and exit
- version**
output version information and exit

AUTHOR [top](#)

Written by F. Pinard.

REPORTING BUGS [top](#)

Report bugs to: bug-coreutils@gnu.org
GNU coreutils home page: <<https://www.gnu.org/software/coreutils/>>
General help using GNU software: <<https://www.gnu.org/gethelp/>>
Report any translation bugs to
<<https://translationproject.org/team/>>

COPYRIGHT [top](#)

Copyright © 2026 Free Software Foundation, Inc. License GPLv3+:
GNU GPL version 3 or later <<https://gnu.org/licenses/gpl.html>>.
This is free software: you are free to change and redistribute it.
There is NO WARRANTY, to the extent permitted by law.

SEE ALSO [top](#)

Full documentation <<https://www.gnu.org/software/coreutils/ptx>>
or available locally via: info '(coreutils) ptx invocation'

COLOPHON [top](#)

This page is part of the *coreutils* (basic file, shell and text manipulation utilities) project. Information about the project can be found at <<http://www.gnu.org/software/coreutils/>>. If you have a bug report for this manual page, see <<http://www.gnu.org/software/coreutils/>>. This page was obtained from the tarball coreutils-9.11.tar.xz fetched from <<http://ftp.gnu.org/gnu/coreutils/>> on 2026-05-24. If you discover any rendering problems in this HTML version of the page, or you believe there is a better or more up-to-date source for the page, or you have corrections or improvements to the information in this COLOPHON (which is *not* part of the original manual page), send a mail to man-pages@man7.org

GNU coreutils 9.11

April 2026

PTX(1)

HTML rendering created 2026-05-30 by [Michael Kerrisk](#), author of *The Linux Programming Interface*.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look [here](#).

Hosting by [jambit GmbH](#).

