
# SIMPLE PROJECT ON CISCO PACKET

#### WE HAVE HALL

- 1. GUEST HALL
- 2. IT HALL
- 3. HR HALL
- 4. SERVER FARM



#### **FIRST WE TAKE A ROUTER**


AFTER WE TAKE THREE SWITCH AND WE TAKE 4 PC AND 3 SERVER AND ONE SMART PHONE AND ONE WIRELESS DEVICE



## 1. GUEST HALL

WE TAKE ONE SMART PHONE AND WIRELESS DEVICE


FIST WE GO TO THE GUEST PHONE AND GO TO DESKTOP AND CLICK IP CONFIGURATION IPV4 ADDRESS – 192.168.1.100 AND DEFAULT GATEWAY-192.168.1.1 DNS SERVER-192.168.1.222



## 2. IT HALL


WE TAKE TWO PC AND ONE SWITCH
FIRST WE GO IT PC1
AND GO TO DESKTOP AND CLICK
IP CONFIGURATION
IP ADDRESS -192.168.1.3
DEFAULT GATEWAY-192.168.1.1

DNS SERVER-192.168.1.222
AND GO TO IT PC2
IP ADDRESS-192.168.1.4
DEFAULT GATEWAY-192.168.1.
DNS SERVER-192.168.1.222
PING IP IS DONE
AND GO TO WEB BROWSER
ALL IS DINE




## 3. HR HALL

WE GO TO HR ROOM
AND TAKE ONE SWITCH AND
TWO PC
WE GO TO HR PC1 GO TO DESKTOP
AND CLICK IP
IP ADDRESS-192.168.131
DEFAULT GATEWAY-192.168.129
DNS SERVER-192.168.1.222




AND GO TO HR PC2 CLICK IP CONFIG IP ADDRESS-192.168.1.132 DEFAULT GATEWAY-192.168.1.129 DNS SERVER-192.168.1.222




### 4. SERVER FARM


WE GO TO SERVER FARM
WE TAKE THREE SERVER
FIRST GO DHCP SERVER
CLICK IP CONFIG
IP ADDRESS-192.168.1.220
DEFAULT GATEWAY-192.168.1.193
DNS SERVER-192.168.1.222



GO TO DNS SERVER
CLICK IP CONFIG
IP ADDRESS -192.168.1.222
DEFUALT GATEWAY-192.168.1.193
DNS SERVER-192.168.1.222




AND GO TO THIRD SERVER FARM CLICK IP CONFIG IP-192.168.1.221 DEFULT GATEWAY-192.168.1.193 DNS SERVER-192.168.1.222



### **CONFIGURATION**

#### WE HAVE ONE ROUTER AND THREE SWITCH


- > ROUTER TO IT SWITCH
- ✓ ENABLE
- ✓ CONFT
- ✓ HOSTNAME IT-SWITCH
- ✓ ENABLE SECRET CLASS
- ✓ SERVICE PASSWORD ENCRYPTION
- ✓ BANNER MOTD "AUTHORIZED A CCESS ONLY
- ✓ LINE CONSOLE 0
- ✓ PASSWORD CISCO
- ✓ LOGIN
- ✓ LINE VTY 0 15
- ✓ PASSWORD CISCO
- ✓ LOGIN
- ✓ LOGG
- ✓ LOGGIN SYNS



### **CONFIGURATION**

#### > Router to HR-Switch

- ✓ ENABLE
- ✓ CONFT
- ✓ HOSTNAME HR-SWITCH
- ✓ ENABLE SECRET CLASS
- ✓ SERVICE PASSWORD ENCRYPTION
- ✓ BANNER MOTD "AUTHORIZED A CCESS ONLY
- ✓ LINE CONSOLE 0
- ✓ PASSWORD CISCO
- ✓ LOGIN
- ✓ LINE VTY 0 15
- ✓ PASSWORD CISCO
- ✓ LOGIN
- ✓ LOGG
- ✓ LOGGIN SYNS



## **CONFIGURATION**

Router to Server Farm

