



PC
CD
ROM

MUSIC 2000™



Codemasters® 

© 2000 Jester Interactive and The Codemasters Software Company Limited and Codemasters Limited ("Codemasters") All Rights Reserved. "Codemasters" is a registered trademark of Codemasters Limited. "MUSIC 2000" is a trademark of Codemasters. Developed by Jester Interactive. Published by Codemasters. Private and domestic use only. All rights of the producer and of the owner of the compositions reproduced in MUSIC 2000 are reserved. Unauthorised copying, rental, lending, public access or access for fee, public performance or display, printing off, broadcasting, networking and cable transmission or supply OF THE COMPOSITIONS is prohibited.

MCLACDEU50

PRECAUTIONS

- Do not touch the surface of the disc when handling, hold it by the edge.
- To keep the disc clean, wipe gently with a soft cloth. Keep the disc scratch free
- Keep the disc away from extremes of temperature, direct sunlight or exposure to excessive moisture.
- Never use a cracked or warped disc or one that has been repaired using adhesives. This could lead to operating problems.

EPILEPSY WARNING

WARNING READ BEFORE USING YOUR VIDEO GAME SYSTEM

A very small percentage of individuals may experience epileptic seizures when exposed to certain patterns or flashing lights. Exposure to certain light patterns or backgrounds on a television screen or while playing video games may induce an epileptic seizure in these individuals. Certain conditions may induce undetected epileptic symptoms even in persons who have no prior history of prior seizures or epilepsy. If you, or anyone in your family, has a epileptic condition, consult your physician prior to playing. If you experience any of the following symptoms while playing a video game: dizziness, altered vision, eye or muscle twitches, loss of awareness, disorientation, any involuntary movement, or convulsions, IMMEDIATELY discontinue use and consult your physician before resuming play.

PIRACY NOTICE



Copying commercial games, such as this, is copyright infringement and is a criminal offence. So is using copied games, so is possessing copied games. Copying and re-supplying games can lead to a term of imprisonment for up to 10 years.



THINK OF A COPIED GAME LIKE STOLEN PROPERTY.

If you are aware of someone who is involved in copied games please telephone ELSPA CRIME UNIT on 01386 833810, who will be pleased to hear from you.

© 2000 Jester Interactive and The Codemasters Software Company Limited. ("Codemasters") All Rights Reserved. "Codemasters"® is a registered trademark of Codemasters Limited. For home use only. Unauthorised copying, adaption, rental, lending, re-sale, arcade use, charging for use, broadcast, cable transmission, public performance, distribution or extraction of this product or any trademark or copyright work that forms part of this product are prohibited. Developed by Jester Interactive. Published by Codemasters. Private and domestic use only.

"Where's Jack The Ripper" composed by Grooverider. Written by Ray Bingham, Published by Clevertogs Limited/Chrysalis Music Limited
"Double Flash" composed by Leftfield. Written by Neil Barnes and Paul Daley, Published by Hard (UK) Hands Publishing Limited / Chrysalis Music Limited
All rights of the producer and of the owner of the compositions reproduced in Music 2000 are reserved. Unauthorised copying, rental, lending, public access or access for fee, public performance or display, printing off, broadcasting, networking and cable transmission or supply OF THE COMPOSITIONS is prohibited.



MUSICTM 2000

Codemasters[®]

EPILEPSY WARNING

Please read before using this product

Some people are susceptible to epileptic seizures or loss of consciousness when exposed to certain flashing lights or light patterns in everyday life.

Such people may have a seizure whilst playing certain video games. This may happen even if the person has no medical history of epilepsy or has never had any epileptic seizures.

If you or anyone in your family has ever had symptoms related to epilepsy (seizures or loss of consciousness) when exposed to flashing lights, consult your doctor prior to using this product.

If you or your child experience any of the following symptoms: dizziness, blurred vision, eye or muscle twitches, loss of consciousness, disorientation, any involuntary movement or convulsion, while playing a video game, immediately discontinue use and consult your doctor.

Precautions to take whilst using this product

- Don't sit too close to the monitor
Make sure you are a good distance away.
- Preferably play the product on a small monitor.
- Avoid using if you are tired or have not had much sleep.
- Make sure that the room in which you are playing is well lit.
- Rest for at least 10 to 15 minutes each hour that you play a video game.

ROYALTY-FREE LICENCE



You are entitled to a world-wide royalty-free licence to make, use, sell, distribute and publish any works that you create with **MUSIC 2000™** or using any audio or video components of **MUSIC 2000™** provided that any such works are clearly marked on the media or packaging with the above **MUSIC 2000™** logo and that you have posted to us acknowledgement of your intended use.

This acknowledgement should be in the form of brief details about the works you have created and contact information and should be posted to:

MUSIC 2000™ Registration Dept., P.O. Box 6, Leamington Spa, Warwickshire, UK.

This licence does not include the right to use any recordings or components of '**MUSIC 2000™**' in any commercial music or video creation product. No licence is granted in respect of the original compositions by Grooverider and Leftfield.

TABLE OF CONTENTS

Tutorial	3
Making A Song Using Riffs	10
Creating Your Own Riffs	13
Sampling / Editing Samples	19
Making a Video Using Clips	23
Creating Your Own Clips	25
Music Jam	28
Loading & Saving	31
Playing your own Audio CD's	33
Options Menu	34
Frequently Asked Questions	35



Installation of **MUSIC 2000™**

Before proceeding, ensure that you close as many programs and functions as possible before installing and running the game.

Insert the **MUSIC 2000™** CD into your CD-ROM drive. **MUSIC 2000™** uses the Autorun feature of Windows®95/98 so the installation program should appear automatically. If the Autorun feature is disabled on your computer then click on the [START] button then [RUN], type D:\SETUP.EXE (where D: is the letter of your CD-ROM drive) then click [OK]. Alternatively, double-click on [My Computer], double-click on the CD-ROM drive icon, double-click on [SETUP.EXE].

A menu window will now appear with the following choices:

- Play **MUSIC 2000™**
- Install **MUSIC 2000™**
- Uninstall **MUSIC 2000™**
- Test **MUSIC 2000™** requirements
- Exit **MUSIC 2000™** launcher

- Clicking Play will launch **MUSIC 2000™**.
- Clicking Install will launch the installation program.
- Clicking Uninstall will remove **MUSIC 2000™** from your computer.
- Clicking Test **MUSIC 2000™** Requirements will determine if your computer can run **MUSIC 2000™**.
- Clicking Exit **MUSIC 2000™** launcher will exit from the **MUSIC 2000™** launcher.

At the start of installing **MUSIC 2000™** you will be given the option to install DIRECTX 7, if this is not already installed. DIRECTX 7 must be installed on your computer to play **MUSIC 2000™**.

TUTORIAL

Congratulations and thank you for buying **MUSIC 2000™**. You don't need to try and digest the whole manual now, but we suggest that you read through this Tutorial section. In this section, you'll find details on the on-line help, as well as the menu system. Together, these features should allow you to navigate through **MUSIC 2000™** with ease.



Getting Started

Loading and playing a demo song.

MUSIC 2000™ comes with several demonstration songs. These give you an example of the diverse range of music you can make, and also allow you edit, remix and examine the tracks, which have been written by a number of different musicians. All these songs also contain a full video, which you can edit and examine. Right, so how do you play one of these demos? Firstly, a quick guideline - as a general rule the left mouse button carries out actions and the right mouse button brings up menus. There is also a shortcut menu across the top right of every screen - each icon represents a different action which can be accessed by left clicking or by pressing the respective function key. Pressing Esc takes you back to the previous screen or menu.

Once you have started **MUSIC 2000™**, you will find yourself on the main track screen. The main menu icons across the top left allow you to choose between the different modes. Click on the '**Load and Save**' icon to see all the songs/videos that are supplied with **MUSIC 2000™** within the directory called '**Songs**'. Move over one of the songs and click to select

the track. Click on the load icon and the track will load up. By default, all the elements of a track will load so if a track has both music and video, they will be both be loaded. If you want to load just the music, or even just particular riffs, right click and toggle the track's individual components on or off before loading.

Once the song is loaded, click OK and then select the '**Song Track**' option. You will now see the song on the screen. Press the spacebar to start and stop the song. To watch the video as well, go back to the main menu icons, choose '**Video Track**' and play the song from there. You will see the video playing in a box on the screen - you can make it fill the whole screen by right clicking and selecting 'Full View Screen'.

Repeat this process to play any of the demonstration songs.

Creating your own new song

Firstly you need to make sure that you don't have a song or video loaded in. If you have just loaded **MUSIC 2000™**, you will be alright, but if you have loaded in any of the demonstration songs, you will need to clear the music and video. To do this, go to the main menu icons and select the '**Options**' menu. Then select '**Clear All**' to delete


all music and video so we can start from a blank canvas. Go back to the top menu, and select the main **'Song Track'** option.

Making a song is very simple. Right click for a menu to appear. Choose the **'Riff library'** option (note that there is a shortcut to this option displayed on screen, which you can use later to save you time. The particular shortcut is F6). Use the scroll bars to move up and down each list of riffs or change the instrument section you are in. If you keep scrolling right you will see there are lots of different sections, split into Beat, Drum n Bass, House, Rock, Techno and Trance.

Press F1 to listen to any of these riffs. Once you've found a riff you like, click on it and you'll be taken back into the main track screen. Click again to lay down the riff - you're best off putting your new riff onto track 1 (at the top left hand side of the screen). Note that you can put it down as many times as you want. If you make a mistake, press Delete to delete it.

To play the riff, go back to the left hand edge of your song and press Space. When the timer reaches your riffs you will hear them play. Press Space again to stop the track.

You can now repeat this process, pressing F6 as a shortcut to go into the library. Try putting a bass-line down first, and then a drumloop underneath it, and then a melody. You're making music!



Music Jam

Music Jam is an almost immediately accessible and fun way of making music that up to 4 players can use at once over a network / via the Internet. You can also play Music Jam on your own – just choose **'Single Player Jam'** and Music Jam will start.

To loop sounds, simply press Shift and the Function keys. Hold down the number pad keys to play non-looping samples and use the keyboard to play the two pianos provided. To change any sounds, right click.

A full explanation is available in the Music Jam section later in this manual.

FULL MANUAL

The main screen layout



At the top left of the screen, you will see the six main menu icons:



Song Track: Create and play songs



Video Track: Create and play videos



Music Jam: Jam with 1-4 players



Load and Save: Load and save songs and information



CD Player: This lets you play audio CDs, or record samples from them



Options: Allows you to clear songs / video and get sound / video related options.

At the top centre of the screen is a box telling you details of the song currently being played: its tempo (in beats per minute) both numerically and graphically, current and overall time in hours, minutes and seconds, amount of memory the song takes up and its name. At the top right is the on-screen menu.

Most of the screen is taken up with the song track display. There are 99 channels. Each channel is 999 bars long (more than enough for even the longest of songs), and is split into boxes.

Each box represents a bar of your song. Every four bars there is a light blue box to represent the start of each four-bar section. There are scroll bars on the right hand side and also below the main track display, which show where within the screen you are. Under the track display are numbers displaying the bar number of each bar on the screen. As you may have guessed, time moves horizontally. The start of your song is at the left hand side of the screen, and as your song plays, the song will move to the right.



Song Track Shortcuts

F1	Paste riff
F2	Delete riff
F3	Play
F4	Area selection
F5	Riff palette
F6	Riff library
F7	Song start
F8	Song end
F9	Song bottom
F10	Change mixer settings
F11	Undo
F12	Help

Online Help

Wherever you are within **music 2000™**, refer to the shortcut icons on the top right of the screen or right click to display a menu showing you all the options available for the current screen. Move up and down the menu and choose the option you want.

If you want more information about any of the options, move down to 'Help' at the bottom of every menu. This will allow you to choose which item you'd like help on.

Click whichever option you want for a full description of what the option does.



Redo / Undo

If you make a mistake, most menus have an **'Undo'** option- selecting this reverses the last action you made. If you then decide that you did want to perform the action, you can select **'Redo'** to reverse the **'Undo'** option. The Undo shortcut is **CTRL + Z** and **CTRL + Y** will Redo.

Volume



Underneath the 99 channels are four more channels, each of which has a specific function. The first is the volume channel. The very first bar here can be used to set the volume for the entire song.

Clicking on this bar will allow you to choose the initial volume (at the start of your song), and the final volume (at the end of the bar). This allows you to fade your song in or out. If you just want to alter the volume throughout your song, change the start/end volume.

If you click on any bar other than the first, you will then be asked to select a range of bars, and again you can alter the start and end volumes for your selection. For example, to fade out your song over the last four bars, move to the fourth bar from the end, click and drag the area and when you let go of the mouse button you will be able to change the start and end volume levels in the volume menu.

Reverb



Underneath the volume channel is the reverb channel. Reverb is an effect similar to clapping your hands in a large hall - the sound seems to hang in the air for a while. The first bar allows you to set the reverb setting for the entire song.

You can also change the type of reverb and its depth, delay and feedback rate.

If you want the reverb to alter over a number of bars, click on the first bar, and then move over and click on the last bar of the sequence. You can then set the depth, delay and feedback settings for both the start and end of the sequence, but only in conjunction with **'Note Repeat'**.

BPM



Underneath the reverb channel is the BPM channel. This allows you to set the tempo (number of beats per minute) of your song. The first bar allows you to set the tempo for the entire song. If you want a constant tempo, alter the start/end setting. Otherwise, you can get the song to speed up or slow down by changing the start and end tempos. If you want your song to speed up or slow down over a number of bars, you can select the first bar, select the final bar, and then set the start and end tempos.

Transpose Key



The track at the very bottom is the transpose key track, allowing you to change the key of all the music. Simply select the bar you want to transpose and then choose the key you want.



Most of the standard riffs are in the key of 'C', so a very simple key change is to cycle repeatedly between C, F, G and then C again. If you don't want to alter the default key, choose the icon on the left. You can also specify whether you want the key to be changed into a minor or major key. Select **'None'** if you want to leave the minor/major notes as they were by default. Please note that you need to select the key to transpose to before placing the riffs into that bar.

World View

If you go to the menu from the song track screen and choose **'World View'** you will be able to see 60 channels on screen at once, as well as 96 bars as opposed to the standard 24. This can be very useful to get an overall view of your entire track, and to see how it is working. To get back to the normal view, go to the menu, and select **'Cancel World View'**.



MAKING A SONG USING RIFFS

Making a song using the riff library is very easy, essentially placing musical building blocks together.

The riff library



There are over 1000 different riffs split into different musical styles and sections. To access the riff library from the standard song track screen, right click and select Riff Library from the menu or use the shortcut **F6**. Within the riff library, the top word is the style of music (Beat, Drum'n'Bass, House etc) and below that you can see the type of riff (Bass lines, Drum loops, Melody etc..). Scrolling left and right will change the type of riff. If you keep moving in one direction, you will move into a different style of music.

Scrolling up and down will allow you to see all the different riffs within a section.

If you want to hear (audition) a riff, press **F1** or right click for a demo. If you want to place a riff into your song, simply click on it.

Placing a riff into your song

Once you have loaded a riff in, you will find yourself back on the song track screen. You can move around the screen, using the left button to place the riff. Note that riffs can be between 1 and 8 bars long, and also some of the more complicated riffs can use several channels. Therefore, if you can't place the current riff in the song, it may be that it doesn't fit. Move to a different place and try again.

You can place any riff in any position. Placing two identical riffs next to each other horizontally will cause the riff to repeat and placing two identical riffs underneath each other will double the riff's volume.

Playing the current song

You can press Space to play the song from the current point. Pressing Space also stops the song. If you want to hear the song right from the start press **CTRL HOME** and then press **Space**. You can also *'Go to song start'* and *'Go to song end'* via the shortcut icons on the top right of the screen

Deleting riffs

If you want to delete a riff, simply move over its icon, and press **Delete**.

Copying and pasting riffs



You can copy and move an area of any size - from just one bar, to a large block of bars. Firstly, move to the top left hand corner of the area you want to select.

You can select an area in one of two ways: click and drag or right click to bring up the menu and choose *'Area Selection'*.

Once you have selected the area, right click to choose what action to take - you can choose to copy the area (leave the original selection there, and place a copy somewhere else), cut the area (delete the original selection, and place it somewhere else), or join riffs (which allows you to merge a number of riffs into one big riff). Shortcuts are available through the on-screen list and are also detailed in the help menu.

If you have chosen to Cut or Copy, you can then move the selection box to wherever you want to place your selection, and left click to place it.

Changing the volume of riffs

Move over the riff you want to change and choose *'Change riff volume'* from the menu. To alter the volume throughout the riff, change the start / end section. Otherwise, you can set the start and end volumes in order to make the riff get louder or quieter. The maximum volume of a riff is 100. If the riff still isn't loud enough, either lower the volume of other riffs in your song, or place an identical copy of the riff below it.

Riff palette

Once you have used a riff once in your song, it will be placed into your Riff palette. You can bring this up by pressing **F5** or by choosing *'Riff Palette'* from the menu. This makes it quick and easy to find a riff that you have already used. If you create your own riffs, they are also placed here.

CREATING YOUR OWN RIFFS

MUSIC 2000™ allows you to create your own riffs, note by note, using over 2000 instrument samples. You can also record samples from any audio CD for use instead of a standard sample (see section 4, p19).

Starting a blank riff

On the Song Track screen, go to the menu and choose **'Riff Editor'**. You can then move left and right to decide how long you want your riff to be – from 1 to 8 bars. You can also decide how many channels you want your riff to use – this is determined by how many vertical bars are selected when you first select Riff Editor (for example a 4-bar riff with 3 channels equates to a 4x3 rectangle of bars). For most tunes and bass-lines you will only need one, but if you want two notes to play at the same time, you will need to use two channels, and so on. The maximum number of channels you can use in one riff is 12.



Once you are happy with the size of your riff, left click to enter the riff editor screen – this isn't as complicated as it may look!

On the left hand side are the numbers 1 to 6, representing octaves on a keyboard. The current octave is highlighted. Next to these numbers are a representation of the keys of a piano. It is essentially a piano on its side, six octaves long. In a similar way to the standard song track screen, time goes from left to right. Don't worry about the icons on the right hand side of the screen for now - they provide advanced effects you won't need to use at the moment.

At the bottom of the screen are the channel numbers. Most of the time, you will only use one channel, but if you are making more complicated multi-channel riffs, the currently selected channel will be highlighted.

Choosing an instrument / sample



There are a vast number of different instruments you can choose from. Enter the menu and choose **'Sample library'**. This works in a very similar way to the riff library. Scroll left and right to change the type of sample and up and down to see all the samples within a particular section. Pressing F1 demos a sample, and once you are happy with a sound, you can choose to load a sample at one of three different rates. A sample rate affects the quality of the sample - 11 kHz is the lowest quality, and 44 kHz is the highest quality. It's best to use 44kHz throughout your songs but in the unlikely event of your PC running out of memory, you can load in samples recorded at a lower rate.

Placing riffs into the loaded sample list

Once you have chosen a sample, you will be shown a list of all the samples you currently

have loaded in. If you have used any standard riffs in your song, the samples used will be in here already. Choose a blank slot for your sample, and left click. Note that you can replace a loaded sample with the new sample you have just chosen.

Recording

There are two ways to record a riff: step-time and real-time.

Step-time record

In step-time, you place the notes wherever you like by left clicking and then press Space to hear the riff. Move up and down to alter the pitch of the note. If you move up past the highest note of the keyboard and return to your original position at the bottom you have risen a whole octave. Similarly, moving down when you are at the bottom of the riff will lower the octave. Moving left and right alters the timing of the note.

The lighter coloured squares show each beat of each bar (there are four beats in a bar). The best way to understand step-time recording is to place a few notes in different places, move to the left hand side, and play the riff.

If you make a mistake, you can press **Delete** to delete a note. Dragging and clicking makes the note hold for a longer amount of time.

Real-time record

If you would rather use your own rhythm to tap the notes in, choose **'Real-time recording'** from the menu. You will hear a metronome clicking the beat. Move up and down to alter the pitch of a note, and then left click at the right time to enter a note there. If you make a mistake, you can press **Delete**.

You can also use a Midi keyboard to input notes in real-time record mode, or hone your skills in **'Real-time Practice'** mode.

Note parameters



For each note, you can alter any of the note parameters. A word of caution - these are not for beginners. Don't think about using these until you are confident with the riff editor. You can enter the note parameters section by selecting any of the **'Note Parameters'** from the right hand side of the Riff Editor while highlighting the note you wish to edit.

Note muting

You can use this to mute (silence) a note. When the icon is red, the note has been muted.

Note pitch-bend

This applies pitch-bend between two notes.

AM Channel (Low Frequency Oscillator)

This is a more advanced effect. When you choose this, a new channel will be created. Anything you place into this new channel will not be played as normal. Instead, the volume of whatever is placed in the new channel will directly alter the pitch of whatever is placed in the current channel. Try it and see!

Note volume

This allows you to alter the volume of the note.

Note repeat

This allows you to repeat a note very quickly, allowing you eight subdivisions within one of the blocks. Move left and right to change the subdivision, and move up and down to alter the status. A yellow block means that the note will play with reverb, a red block means the note will play without reverb, and a black block means that the note won't play at all.

Note vibrato

There are two settings for the vibrato of a note (the wobbling in pitch of a note). The first is the vibrato depth, and the second is the vibrato speed. These control the amount and the speed of the wobble.

Note sample start

This controls the point where a sample starts playing from. For example, if you have a vocal sample that says 'coming soon', you can alter the start point so that the sample just says 'soon'. Using this can create some fantastic new effects from existing samples.

Note effect

There are a large number of different effects that you can use on a note to make it sound a little different. Choose the effect you want from this menu. The best way to understand the difference between the effects is to try them all. If you don't want an effect, choose **'None'**.

Envelopes



Note volume envelope

This lets you alter the volume envelope of a sample. On the graph, time goes from left to right, and the vertical scale is the volume. Therefore, you could make the sound start really loud and then tail off, or start quietly and then get louder. Use the menu to choose from a number of default envelope shapes, or click and drag to alter the position of any of the points. You can also add and delete points from the graph, again using the menu.

As with all of the parameters, any changes you make will be saved with your song.

Note pan envelope

This allows you to alter the stereo position of a sample. Time goes from left to right on the graph and the stereo position runs vertically. Again, you can use the menu to choose from a number of default settings, or else create your own.

Note pitch envelope

The final parameter allows you to alter the pitch envelope of the sample. Time goes from left to right and the pitch runs vertically. Again, there are a number of default settings for you to try out.

Multi-channel riffs



As mentioned earlier, riffs can consist of several channels. Each channel can have one sample playing at a time, so if you want to create a riff with three samples playing simultaneously, you will need to make a three-channel riff. Click on the channel numbers at the bottom of the Riff Editor to toggle through the different channels. The notes in the current channel will be displayed brightly, and other notes from other channels will be dimmed out. This makes it easy to make complicated chords.

Customising your riffs

Using the menu within the riff-editor, you can alter the name and icon for your riff. These options are self-explanatory.

Storing your riffs as palettes

Any riff you create will automatically be stored in the riff palette. This makes it easy for you to quickly find any of the current riffs you have created.

Resizing / cloning riffs

Using the song track menu, you can choose to resize the riff. This will allow you to shrink or grow the riff. Click and drag until you are happy with the new size. Note that if you shrink a riff, you will lose any notes that are removed during this process. You can also 'clone' a riff. This allows you to alter one riff without changing all the other identical riffs in your song. Move over the riff, go into the menu and select **'Clone riff'**. You can now alter this riff without changing any other identical riffs.

Muting riffs

Within the Song Track menu, there is an option to change the 'mute status' of a channel to mute (silence) the whole channel. This can be useful when you want to hear a song without a particular channel playing. Changing the mute status again by clicking on the channel number turns the channel back on.

Splitting riffs

You can split song blocks or individual bars into separate riffs. Move over the riff you want to split up, and select **'Split riff'** from the menu. Once you have split a riff up, you can recombine any parts you want to by selecting them and using the **'join riffs'** command (see section 2 copying and pasting riffs p13).

SAMPLING / EDITING SAMPLES

Legalities

MUSIC 2000™ allows you to record and edit samples from any audio CD, as well as from your soundcards, audio inputs and any WAV file. Please note that this feature is designed for your own personal use - distributing or publishing songs using samples taken from commercial CDs is illegal without permission from the copyright owner. Therefore, if you plan on trying to publish or copy your creations, we strongly advise that you only use the CD sampling feature to record copyright-free samples, such as those found on specially recorded sample CDs.

There are two ways to record samples in **MUSIC 2000™**. You can use the CD player to record samples from audio CDs, and you can record within the riff editor, which takes input from the audio mixer.

Use this to record from your soundcard microphone and line inputs, as well as from other PC software.

The audio mixer can be brought up by clicking on the audio mixer icon on the icon bar.

This will list all the audio inputs on your PC.

You can alter the volume of these, as well as selecting which device is the input device (to be recorded from).

CD Recorder

Click on the main CD player section icon. You will now be prompted to choose **'No video'** or **'Generate video'**. If you want to record samples from the CD, choose **'No video'**. You will now see a CD function bar appear on your screen. Use this to choose a track, play, pause and stop the CD. Click the **'Record'** button when you want to record, and then click again to stop. The recorded sample will be placed into your sample palette.



Audio Recorder

When you are in the riff editor, right click to get the menu up, and select **'Record from PC audio'**. You will then see the sample editor screen. Click the red record icon when you are ready to record and then click the mouse again to stop recording. You can then edit the recorded sample using the sample editor (discussed elsewhere in this manual).

Firstly, start the audio source playing or get

ready to sing with your microphone! As soon as you reach the point that you want to start sampling, click on the **'record'** icon. You will see the bottom counter start to increase, which shows you how much you have recorded. When you want to finish sampling, click on the **'stop'** icon.

Placing a sample into a riff

Go back into the song track screen, and create a new blank riff using the Riff Editor. Instead of going into the sample library, go into the sample palette via the menu. You will see at the bottom of the sample list a new sample called **'Sample 0001'**, which will contain the sound you just recorded.

You can use this just like a normal instrument sample, and place it in your riff. Everything that you can do with a normal sample, you can do with one you have created yourself. See section 3, p13 for more information.



Using the sample editor

The sample editor allows you to edit any sample, whether from **MUSIC 2000™**, or from an audio CD. To enter the sample editor, you need to be in the sample palette screen. Highlight the sample that you wish to edit, press the menu button and choose the **'Edit sample'** option.

You will see a graphical representation of your sample.



Here you can edit your sample in a number of ways.

The three markers

There are three pairs of markers. The top pair represents where your current position in the sample is, and when you are moving this marker around, the hourglass icon on the top right will be highlighted.

The second pair of markers shows the start of the sample edit area and is represented by the left arrow icon. As you move this around, you will see parts of the sample turning into a black background.

The third pair of markers represents the end of the sample edit area. This is represented by the right arrow icon and, again, parts of the sample will have a black background as you move this around.

Sample editor icons

The first three icons are mentioned above.

The fourth icon represents the loop point.

The 'K'-shaped icon shows the size of your sample in bytes (i.e. how much memory it takes up)

The next icon tells you whereabouts in the sample the left of the screen is. This is useful to know if you're zooming in to a section within your sample.

The next icon tells you whereabouts in the sample the right of the screen is.

The final icon shows the size of the current editing zone (the area highlighted in blue).

Cutting, copying, trimming and pasting

In order to select an area within your sample, you need to move the start markers to the start and the end markers to the end of that area. The area will then have a white and pink background and the rest of the sample will have a black background. Copy the highlighted area by choosing the '**Copy**' option from the menu. Paste the area you have just copied using the '**Paste copied area**' option. The '**Cut**' option works in a similar way except that it deletes the area you copy. Trimming is a very useful option, deleting areas with a black background to remove any silent or unwanted areas.

Zooming in / out

You can use the '**Zoom into area**' and '**Zoom out**' options to alter the magnification of the sample in order to concentrate on more detailed areas.

Note: There are some complicated parameters that we don't have room to fully explain here. More details on these can be found in sampling journals, or on the Internet.

Effects

All the effects listed below are accessible via the help menu.

Loop on: Toggle sample loop on/off once it has finished playing

Alter sample ADSR values: Change the note volume envelope

Comb filter: Cut out any unwanted frequencies

All-pass filter: Add delay and feed back to the sample

Reverb filter: Add reverb to the selected area

High / low pass filter: Allow just the high or low frequencies to be heard

Flange filter: Add a flange effect to the selected area

Phase filter: Add a phase effect to the selected area

Weird filter: Add a chorus effect to the selected area

Bandpass filter: Isolate a band of frequencies from your sample

Reverse

This literally reverses the selected area, so it plays backwards. This can create some unique sounds!

Normalise

This alters the volume of the sample so that it will tie in with the other standard samples in **MUSIC 2000™**. If your audio CD is quiet, or if you record a soft section of music, this is very useful for bringing the volume up.

Mixing samples

Combine two samples. Select the first area and choose the '**Copy**' option. Then go to the second sample, select the required area, and choose '**Mix samples**'. The two samples will be mixed together, and you will end up with one sample that contains both sounds. Keep repeating this process to add more and more sounds to one sample.

The sample palette

Optimising the loaded sample list

This removes any sample from the list not being used in the song, for instance if you use a riff, and then delete it. The samples will still be stored in the list until you choose

'Optimise sample list'. This frees up any space taken up by unused samples.

Downgrading and upgrading samples

If your **music 2000™** sample has been recorded at 44kHz, and you want to save memory, you can choose to downgrade the sample. The first time you downgrade, it will change to 22kHz, and then to 11kHz. Similarly, you can downgrade a 22kHz sample to 11kHz. Remember that there will be a drop in sample quality.

Saving your edited samples

Your edited samples are automatically saved with the song. Note that if you edit any default samples that come with **music 2000™**, it won't save the new sample, just the changes you have made.

MAKING A VIDEO USING CLIPS

This is similar to making songs using riffs. There is a large library of video clips, consisting of many different types, from background images, to 3D shapes, cameras and feedback effects.

It's simply a matter of putting different clips together and seeing what happens. The best way to understand **music 2000™** is to get stuck in and experiment.

Videos explained

You can access the video track from the main menu on the top of the screen. There are four main channels, as well as channels for a camera and a DVE (digital video effect). You can put a shape or a background into each of the main four channels. Time goes from left to right in exactly the same way as with the music.

Video Shortcuts

F1	Paste clip
F2	Delete clip
F3	Play
F4	Area selection
F5	Clip palette
F6	Clip library
F7	Expand/collapse clip
F8	Edit clip
F9	Go to video start
F10	Go to video end
F11	Undo
F12	Help

The clip library

This contains a large number of different clips. You can place any of the shape and background clips into the main four channels, and any of the cameras, effects and video clips into their respective channels. Press **F6** or select '**clip library**' from the menu. Demonstrate the clips by pressing **F1** and load in a clip by left clicking. Left click to place the clips into your video, using **Delete** to wipe any mistakes.

Press **space** to play the song and video together, which you will see in the small TV box in the bottom right corner.

Please note: In **music 2000™**, pressing full-screen display will automatically engage your 3D graphics card, doing real justice to your video effects.

Moving and deleting clips

This works in exactly the same way as with the music section (Copying and pasting riffs, section 2, p13).

CREATING YOUR OWN CLIPS

MUSIC 2000™ contains a very advanced video editor to allow you to create your own unique visuals to accompany your songs.

Selecting a blank clip

You can choose a blank clip by choosing **'Edit video clip'** on the menu. Decide how long the clip will be by moving left and right. When you are happy, left click to continue. You must then choose the type of clip - a shape, a background, a particle, some text, or a tunnel effect.



The clip editing screen

You can apply numerous effects and movement to your initial clip type - including colour changes, splines, rotations and scaling. To do this press **'Add clip'** in the current menu. So you now have two clip elements displayed on screen.

Highlight the clip element to be edited. You can edit thousands of different parameters, including the number of shapes in your scene, the layout of objects, the direction of rotations, the size of the main clip element - in fact you can take complete control of the visuals displayed on the screen. Scrolling left and right alters the value of the highlighted clip.

Timeline

This feature allows you to add additional steps to your current video clip. Action in a video clip is made possible by transitions from one step (or a moment in time) to another. You can add many steps to each individual clip element.

The timeline edit function is available in clip edit mode and is used with the global settings to create videos that react to markers placed along the timeline. The markers trigger chosen changes in the clip parameter values. To use this function, click on the timeline, add a trigger, alter a clip parameter value and define the global settings. The video will now display your changed settings when the marker is reached along the timeline.

To add steps to the current clip type, click and drag the flashing green cursor to the position of your choice on the Timeline. You can then click on the current clip element and change its parameters.

These changes will be stored on the Timeline. The Timeline is in essence a series of instructions that will bring life to your video clip - but only when used in conjunction with the Global Settings.



Global settings

If you have left information on the Timeline you can make your video trigger off the notes on a music channel or a function key on your keyboard, amongst other things. So, for example, you can make the background change every time a cymbal is struck. Or you can make an object change size with every beat of the song. The possibilities are endless.

Click on Global Settings. There are three parameter boxes with arrows on either side in the Global Settings panel.

If you toggle through the parameters in the top box you will see that you can set the visual effects to trigger off a specified audio channel (1-99).



If you edit the parameters in the middle box you can make your visuals trigger off -

1. Keyboard function keys
2. Sixteenths of the bar
3. Each beat of the song
4. The first beat of each bar
5. Random parameters.

The box at the bottom defines how the information on the Timeline is played.

1. The cursor can scroll from left to right and back again through each edited stage of the Timeline.
2. The cursor will 'step' through each edited position on the Timeline.
3. The cursor can swiftly ramp up through all the parameter changes and then drop back to the start of the Timeline.
4. The cursor will play the Timeline from one end to the other over the length of the video clip (as represented on the track screen).

The box to the right in the Global section has a slider that can be moved up and down to define the sensitivity of the trigger. Set it to the top for the most sensitive response to the trigger you have added.

The numbers 1, 2, 3 and 4 at the right of the Global section refer to the four video channels. This feature is only accessible from the DVE channel - the channel at the bottom of the video screen.

If you select one of the four numbers, the corresponding channel will be deactivated and not included in the current DVE effect.

Clone Video Clip

Changing or editing an existing video clip will change it throughout the whole arrangement. Avoid this by selecting the Clone Video Clip option (while highlighting a video clip on the video track screen) and creating a new video clip modelled on the existing one. The background colour of the icon will now have changed. Any changes you carry out will not be applied to other versions of the original video clip

Auto-Generating a video

This function will automatically create a video for you - perfect if you have just written some music and want some impressive visuals to go with it.

Select '**Auto-generate video**' from the Video Track menu. You will see there are two auto-generate parameter values that you can adjust before the calculations begin. Select '**Generate video**' and **music2000™** will cook you up a video.



MUSIC-JAM

Music Jam is a quick and easy way to jam on your own, on-line or over a LAN with up to three other players. It's also incredible fun and the results can be seriously impressive. For plain and simple jamming, just get pressing those keys. Once you're familiar with the set-up, you can add a host of effects.

Selecting Jam Mode from the top menu bar will display the Host/Join Jam Session Menu. Click on Host a Jam Session to display the Host Options menu:



The player can change any of these settings.

Server Name - used when joining a session.

Player Name - as seen by other players.

Number Of Players - max number of players in a session.

The initial BPM of the session

Maximum User Template Size – limit the size of the samples used.

On entering the Jam Session the player is given the option of choosing a Template. Templates work in the same way as the Riff Library described earlier in this manual. Closing this menu without selecting a template will not load anything.

The Riff Keys

These are the Function keys **F1** to **F12**. Simply press to play. Press Shift and the key to loop and Shift and the key again to stop looping. Left clicking on the riff key will highlight the key selected light, allowing you to apply Mod Wheel and plugin effects to riffs (see below). Right clicking will display the Riff Library. Left clicking will load the selected Riff and right clicking will let the user Preview the Riff or get Help.

The Instrument Keys

These are the number pad keys 0-9. Just press to play. Left clicking on the instrument key will highlight the key selected light so you can apply effects

(see Mod Wheel and Plugins below). Right clicking will display the Instrument Library.

In Instrument Library, right clicking will preview the Instrument at 44Khz.

Left clicking will display the Sample Library Menu – from here the user can Load/Demo the Instrument or get Help.

The Piano



The Piano Text Box

The keys on the two on-screen pianos are mapped to your PC keyboard, as shown on the keys. Just press the keyboard and you're playing piano! You can play more than one note at once and you can also play both pianos at once – if you're up to it. Left click on the text box to highlight the piano selected light (see Mod Wheel and Plugins below).

Right click will display the Instrument Library. In Instrument Library, right clicking will preview the Instrument at 44Khz and left click

will display the Sample Library Menu - from here the user can Load/Demo the Instrument or get Help.

Selecting Riffs and Instruments

CTRL + Left Click will allow multiple items to be toggled as selected/unselected.

SHIFT + Left Click will allow a range of items to be selected. The range is chosen from the last selected item (left clicked).

The Octave Icon



This adjusts the octave of the current instrument on the piano: left click will jump to a higher octave (Max is 6) and right click will jump to lower octave (Min is 1).

The Mod Wheel



When the mouse is over the mod wheel, text under the mouse will display the current effect and value. Left click and drag will apply the current effect to any keys you have selected (see above) and right click will display the list of available effects for the currently selected items.

The Plugin Window

On entering Jam Mode there will be no plugin loaded. Right clicking on the Text "No Plugin Loaded" will display a list of currently loaded plugins - there are 16 available slots. Left click on a slot to switch to the plugin in that slot while right clicking on a slot will display the Plugin Menu. You can choose to Load / Delete / Reset the plugin for that slot.

Clicking on Load a Plugin will display a further menu of the available plugins.

Selecting a plugin from this menu will load it into the selected slot and make it the current plugin.

The plugin will be applied to the currently selected Music Jam items BUT this is only done when you click in the plugin window. For example, to just have piano1 going through the plugin, select Piano1 and then click in the Plugin Window - piano1 will now be affected by the plugin. The plugin can now be changed on the fly by clicking and holding the left mouse button as you move over the plug-in window.

Selecting other items and clicking in the Plugin Window will over-ride previous selections.

Right click on the plugin name within the window to change to a different plugin.

The key selection lights will change to show which items the plugin is affecting.

The Player Windows

There is a window each for up to 4 Players. The blocks in these windows are only used for internet 4-bar delayed jam.

The main aim of these windows is to let other players know what each other is doing. For instance, when a player uses the piano, a piano icon will be displayed for everyone to see.

BUT, by clicking on the window of say Player 2, your local display will reflect what Player 2 sees on their screen.

This allows you to view what riffs they have loaded, how they play their pianos and what plugins they are using.

Left clicking back on the display will revert back to your display.

Right clicking on the player windows will allow the jam session host to either 'kick off' players or 'ban' them – the latter stops them re-connecting to your session.

The Chat Window

Left clicking on the bottom most text line will allow the user to enter a message that will be sent to all players.

Players can use the scroll bar to scroll back to see a message he/she might have missed.

LOADING AND SAVING

Click on the main Load/Save icon to enter the load/save screen. You will see the default **MUSIC 2000™** directory on your hard drive. Any **MUSIC 2000™** songs will be displayed, as well as 'wav' audio files and 'bmp' bitmap images.



The icons at the bottom are:

LOAD - load a file, doing this deletes any current data.

SAVE – save your song/video/template to the hard disc.

DELETE – delete a file from the hard disc.

INSERT – insert a file into your current song . This doesn't delete your current data.

JUKEBOX – allows you to choose a number of songs, which will be played with full-screen video in the selected order. Useful for demonstrations and parties.

NEW FOLDER – allows you to create a new folder on your hard drive.

SAVE SONG AS 'WAV' FILE – records the current song as one big 'wav' file onto your hard disc. You can then cut this onto recordable CD, convert it to MP3 using an MP3 encoder or use it as a Windows™ sound effect.

Types of save file

You can load in three kinds of file :

M2K files - these can contain song and video data, as well as Music Jams and jam templates.

'Wav' files – these are the standard PC sound file format. You can record or download wav files from the Internet, and put them into your song.

'Bmp' files – these are the standard PC image file. You can put your favourite photos and images into your **MUSIC 2000™** videos. There are many shareware graphics programs available to convert to Bmp files from Internet standard formats such as 'jpg' and 'gif'.

Loading in elements of a song/video

By default, clicking on an M2k file will load in all the video and music elements. However, you can load in individual riffs or clips. To do this, right click on the elements list which will appear just before the file is loaded. Turn off the **'song'** highlight and you will be given a list of all the riffs to choose from. Turning off the **'video'** highlight will give you a list of all the clips to choose from.

PLAYING YOUR OWN AUDIO CD'S

MUSIC 2000™ allows you to play your own audio CD's, while automatically generating a video to fit the songs. The video generation system tries to match the style, pace and content of the visuals to the music.

Automatic video generation

Select **'CD Player'** from the main menu. You will be initially prompted to decide whether you would like it to generate a video or not. You can also alter two settings to affect the style of video generated.



Choose **'Generate video'**, and **MUSIC 2000™** will load in video data to use with the audio CD. This data is random every time, so you will get unique results every time you play an audio CD.

Note: If you choose to generate a video, you will not be able to record samples from an audio CD.

You will then arrive at the CD player screen. In the bottom right corner of the screen are some standard CD player controls. Click the play icon and sit back and watch the video being automatically generated.



OPTIONS MENU



Screen 1

Clear music – clear all musical elements from the current song.

Clear video – clear all video elements from the current video.

Clear all - clear both music and video.

Screen 2

Set graphics device – If you have more than one graphics card, you can choose which one to use here.

Set full screen resolution – alter the resolution of the full-screen video.

Set brightness – alter the brightness of the display.

Set feedback quality – increase/decrease the quality of the feedback effect within the video. If you have a very powerful 3D card, you can raise this higher than normal.

Screen 3

Set audio in device – If you have more than one sound card, you can choose which one to use for input here.

Set audio out device – If you have more than one sound card, you can choose which one to use for output here.

Set volume – alter the master volume for **MUSIC 2000™**.

Set max effects channels – alter the maximum number of channels set aside for effects.

Change mixer settings – edit the current mixer settings.

Screen 4

Set MIDI-IN device – If you have more than one midi device connected, you can choose which one to use here.

Set MIDI input channel – specify the midi channel to be used for inputting notes.

Set lowest MIDI note – specify the lowest MIDI note on your MIDI device.

Set Jam MIDI controller – choose the MIDI controller to use for Music Jam mode.

Midi compatibility

Midi keyboards can be used in two areas of the product:

1) When you are recording in real-time mode, you can use a MIDI device to play notes. If the riff you are editing has multiple channels, you can record more than one note at once, and thus play chords.

2) When you are in Music Jam mode, you can use a MIDI device to play notes on the two virtual keyboards. These are polyphonic, so you can play several notes at once.

Midi settings can be altered within Option screen 4, which is explained above.

F.A.Q.

Q I have just deleted a Riff by mistake, help!

A Don't worry **MUSIC 2000™** has an undo (**Ctrl & Z**) feature in the Song track menu, choosing this will undo the last action taken by the user. You can also redo (**Ctrl & Y**) if you make a mistake using the undo feature.

Q I can never remember the shortcuts.

A If you place your cursor over the shortcut menu in the top right of the screen the action and the relevant short cut will appear next to the cursor arrow.

Q How do I make a copy of a Riff and edit it without affecting the original?

A Paste the Riff you want to copy, then choose **Clone Riff** from the Song track menu. This will make a copy of your Riff but will also enable you to edit it without changing the original. The **Clone Riff** option is handy for making subtle changes to a Riff without having to start from scratch.

Q I have deleted my song from the song track editor using the Clear Music option, but my song had not been saved.

A Sorry! but your song is irretrievable. Remember to always save your songs and videos.

Q In Music Jam mode there seem to be more buttons to press than I have fingers

A If you press the **SHIFT** key and then press an **F** key with a Riff assigned to it, **MUSIC 2000™** will hold that button down for you, leaving fingers free to Jam. To stop **MUSIC 2000™** from playing the Riff, simply press **SHIFT** and the button again.

Q I've recorded a Drumloop from CD but can't seem to get it to loop correctly.

A Try adjusting the BPM. When you have recorded your sample you may have parts that you don't need. Use the **Edit Sample** option (from the **Riff Editor\Sample** palette menu), trim off the unwanted sound and then paste the

sample in the Riff editor. For the sample to loop properly you may need to adjust the BPM (at the bottom of the song track editor) to match the BPM the original was recorded at.

Q My Midi keyboard doesn't seem to work with MUSIC 2000™.

A Make sure your keyboard is set to the right channel. On most Midi keyboards you should be able to select the Output channel. Set this and check that **MUSIC 2000™** is using the same channel (**Options\Midi Options\Set Midi input Channel**) - then you should be able to use your Midi keyboard in **Riff Editor** and **Music Jam** modes.

Q When I record a sample from CD and then listen to the resulting sample in the sample palette, nothing plays.

A The CD device might not be selected. You need to have the recording device selected in Windows before starting **MUSIC 2000™**. To do this, go to **Windows Control Pane\Multimedia** and select Record control.

Here you have a choice of devices to record from, so if it's CD Audio you want to record then make sure it is selected on this screen.

Q I have a Voodoo2 card in my PC but I'm unable to use the Video Track editor.

A If your Primary Display card does not support Direct 3D then you will not be able to use **MUSIC 2000™** video capabilities. If you have a Voodoo2 or Voodoo1 then you will need to select it from within **MUSIC 2000™**. To do this, simply enter *Options\Video Options* and choose **Set Graphics Device** - you should then be able to select your Voodoo card from this screen.

Note: always remember to use the latest drivers for your graphics device.

Further FAQ's will be published on our website - www.codemasters.com

CODEMASTERS TECHNICAL SUPPORT

Tel: 01926 816044
Fax: 01926 817595

Lines are open between
0900-1730 Monday, 0800-2000 Tuesday to Friday, 1000-1600 Saturday.

Before you call the Technical Support line, please check that you have read the **MUSIC 2000™** help file, which can be found on the **MUSIC 2000™** CD Rom.

To access the help file

1. Double-click on my computer on the Windows 95/98 desktop.
2. Right-click on your CD Rom drive.
3. Left-click on Explore.
4. Double-click on M2K.HLP.

If your answer is not on disc, please make sure you have the following details before you call the Technical Support line:

- A detailed description of the problem
- If it is repeatable, under what conditions?
- Your brand of PC (Dell, Gateway, Compaq, IBM etc.)
- Your processor brand & type (Intel Pentium 266, Cyrix 200 etc.)
- The make and model of any video / 3D graphics cards in your computer, (Righteous 3DFX, Matrox Mystique etc.) and the version number of the driver for this.
- The make and model of your CD-ROM Drive (Panasonic 562 Double-Speed etc...)
- BIOS version and date. This is displayed soon after the power-on. (AMIBIOS, 1992 etc...)
- The make and model of your sound card (SoundBlaster 32 etc..)
- Your DirectX version (e.g. 6 or 7)
- Your operating system (e.g. Win95, Win98, Windows NT)

Codemasters E-mail
custservice@codemasters.com

Codemasters postal address
Codemasters Limited
Technical Support / Customer Services,
PO Box 6,
Leamington Spa,
Warwickshire,
CV47 2ZT,
UK

Codemasters website
www.codemasters.com

Codemasters' website includes technical support,
as well as news about other Codemasters games.

NOTICE

Codemasters Limited reserves the right to make any changes to this product or this manual at any time without notice.

This product and this manual are under copyright. All Rights Reserved.

Codemasters makes certain limited warranties with respect to the software and the media for software. In no event shall Codemasters be liable for any indirect, consequential or special damages.

Limited Warranty

Nothing contained herein shall affect your statutory rights.

Codemasters warrants to the purchaser that the media on which the software program is recorded will be free from defects in materials and workmanship for a period of 90 days. Defective media will be replaced within this period if the product is returned to Codemasters by recorded delivery, with a description of the defects, the return address, and the purchase receipt.

This warranty does not cover media which has been damaged or misused, nor does it cover the software programs themselves, which are provided "as is".