

General MIDI instrument codes

The following table lists the standard sequence of instruments (timbres) which are specified by General MIDI. The number to the left of the instrument name is the number for the instrument in General MIDI.

Piano Timbres:

- 0 Acoustic Grand Piano
- 1 Bright Acoustic Piano
- 2 Electric Grand Piano
- 3 Honky-tonk Piano
- 4 Rhodes Piano
- 5 Chorused Piano
- 6 Harpsichord
- 7 Clavinet

Chromatic Percussion:

- 8 Celesta
- 9 Glockenspiel
- 10 Music Box
- 11 Vibraphone
- 12 Marimba
- 13 Xylophone
- 14 Tubular Bells
- 15 Dulcimer

Organ Timbres:

- 16 Hammond Organ
- 17 Percussive Organ
- 18 Rock Organ
- 19 Church Organ
- 20 Reed Organ
- 21 Accordion
- 22 Harmonica
- 23 Tango Accordion

Guitar Timbres:

- 24 Acoustic Nylon Guitar
- 25 Acoustic Steel Guitar
- 26 Electric Jazz Guitar
- 27 Electric Clean Guitar
- 28 Electric Muted Guitar
- 29 Overdriven Guitar
- 30 Distortion Guitar
- 31 Guitar Harmonics

Bass Timbres:

- 32 Acoustic Bass
- 33 Fingered Electric Bass
- 34 Plucked Electric Bass
- 35 Fretless Bass
- 36 Slap Bass 1
- 37 Slap Bass 2
- 38 Synth Bass 1
- 39 Synth Bass 2

String Timbres:

- 40 Violin
- 41 Viola
- 42 Cello
- 43 Contrabass
- 44 Tremolo Strings
- 45 Pizzicato Strings
- 46 Orchestral Harp
- 47 Timpani

Ensemble Timbres:

- 48 String Ensemble 1
- 49 String Ensemble 2
- 50 Synth Strings 1
- 51 Synth Strings 2
- 52 Choir "Aah"
- 53 Choir "Ooh"
- 54 Synth Voice
- 55 Orchestral Hit

Brass Timbres:

- 56 Trumpet
- 57 Trombone
- 58 Tuba
- 59 Muted Trumpet
- 60 French Horn
- 61 Brass Section
- 62 Synth Brass 1
- 63 Synth Brass 2

Reed Timbres:

- 64 Soprano Sax
- 65 Alto Sax
- 66 Tenor Sax
- 67 Baritone Sax
- 68 Oboe
- 69 English Horn
- 70 Bassoon
- 71 Clarinet

Pipe Timbres:

- 72 Piccolo
- 73 Flute
- 74 Recorder
- 75 Pan Flute
- 76 Bottle Blow
- 77 Shakuhachi
- 78 Whistle
- 79 Ocarina

Synth Lead:

- 80 Square Wave Lead
- 81 Sawtooth Wave Lead
- 82 Calliope Lead
- 83 Chiff Lead
- 84 Charang Lead
- 85 Voice Lead
- 86 Fifths Lead
- 87 Bass Lead

Synth Pad:

- 88 New Age Pad
- 89 Warm Pad
- 90 Polysynth Pad
- 91 Choir Pad
- 92 Bowed Pad
- 93 Metallic Pad
- 94 Halo Pad
- 95 Sweep Pad

Synth Effects:

- 96 Rain Effect
- 97 Soundtrack Effect

Ethnic Timbres:

- 104 Sitar
- 105 Banjo

Sound Effects:

- 112 Tinkle Bell
- 113 Agogo

98Crystal Effect	106Shamisen	114Steel Drums
99 Atmosphere Effect	107Koto	115Woodblock
100Brightness Effect	108Kalimba	116Taiko Drum
101Goblins Effect	109Bagpipe	117Melodic Tom
102Echoes Effect	110Fiddle	118Synth Drum
103Sci-Fi Effect	111Shanai	119Reverse Cymbal

Sound Effects:

120Guitar Fret Noise	124Telephone Ring
121Breath Noise	125Helicopter
122Seashore	126Applause
123Bird Tweet	127Gun Shot

Instruments can be selected by using the MIDI command byte (0xc0) followed by a data byte which is one of the above numbers (minus 1).

In General MIDI, Channel 10 is reserved for percussion sets. Here is a list of the percussion instruments assigned to each MIDI note number when using General MIDI Channel 10:

35 Acoustic Bass Drum	51 Ride Cymbal 1	67 High Agogo
36 Bass Drum 1	52 Chinese Cymbal	68 Low Agogo
37 Side Stick	53 Ride Bell	69 Cabasa
38 Acoustic Snare	54 Tambourine	70 Maracas
39 Hand Clap	55 Splash Cymbal	71 Short Whistle
40 Electric Snare	56 Cowbell	72 Long Whistle
41 Low Floor Tom	57 Crash Cymbal 2	73 Short Guiro
42 Closed High Hat	58 Vibraslap	74 Long Guiro
43 High Floor Tom	59 Ride Cymbal 2	75 Claves
44 Pedal High Hat	60 High Bongo	76 High Wood Block
45 Low Tom	61 Low Bongo	77 Low Wood Block
46 Open High Hat	62 Mute High Conga	78 Mute Cuica
47 Low Mid Tom	63 Open High Conga	79 Open Cuica
48 High Mid Tom	64 Low Conga	80 Mute Triangle
49 Crash Cymbal 1	65 High Timbale	81 Open Triangle
50 High Tom	66 Low Timbale	