### Python 3 - Tkinter Frame

The Frame widget is very important for the process of grouping and organizing other widgets in a somehow friendly way. It works like a container, which is responsible for arranging the position of other widgets.

It uses rectangular areas in the screen to organize the layout and to provide padding of these widgets. A frame can also be used as a foundation class to implement complex widgets.

### Syntax

Here is the simple syntax to create this widget -

```
w = Frame ( master, option, ... )
```

### **Parameters**

- master This represents the parent window.
- options Here is the list of most commonly used options for this widget. These options can be used as key-value pairs separated by commas.

```
# !/usr/bin/python3
from tkinter import *
root = Tk()
frame = Frame(root)
frame.pack()
bottomframe = Frame(root)
bottomframe.pack( side = BOTTOM )
redbutton = Button(frame, text = "Red", fg = "red")
redbutton.pack( side = LEFT)
greenbutton = Button(frame, text = "Brown", fg="brown")
greenbutton.pack( side = LEFT )
bluebutton = Button(frame, text = "Blue", fg = "blue")
bluebutton.pack( \ side = LEFT \ )
blackbutton = Button(bottomframe, text = "Black", fg = "black")
blackbutton.pack( side = BOTTOM)
root.mainloop()
```

# Result

When the above code is executed, it produces the following result -



Sr.No.	Option & Description
1	bg  The normal background color displayed behind the label and indicator.
2	bd  The size of the border around the indicator. Default is 2 pixels.
3	<b>cursor</b> If you set this option to a cursor name ( <i>arrow, dot etc.</i> ), the mouse cursor will change to that pattern when it is over the checkbutton.
4	height The vertical dimension of the new frame.
5	highlightbackground  Color of the focus highlight when the frame does not have focus.
6	highlightcolor  Color shown in the focus highlight when the frame has the focus.
7	highlightthickness Thickness of the focus highlight.
8	relief  With the default value, relief = FLAT, the checkbutton does not stand out from its background. You may set this option to any of the other styles
9	width  The default width of a checkbutton is determined by the size of the displayed image or text. You can set this option to a number of characters and the checkbutton will always have room for that many characters.

## Example

Try the following example yourself -