

Step 1:



(Xming)

N.B.: Xming server should be always on

### *Write the Program*


Step 1:



(Putty)

Step 2:


Give IP address as 172.24.73.80 and port no. as 22



Click on *Open*

Step 3:

In login as : **Your Roll No.** and password : **user123**



After login, you will be greeted with this screen

```
172.24.73.80 - PuTTY
login as: 1610501001
1610501001@172.24.73.80's password:
Welcome to Ubuntu 16.04.5 LTS (GNU/Linux 4.7.0.intel.r5.0 x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:        https://ubuntu.com/advantage

7 packages can be updated.
5 updates are security updates.

Last login: Tue Jul 31 16:54:29 2018 from 172.24.73.191
$
```

Step 4:

Write the program

\$ cd masm

\$ nano prog\_name.asm

After saving the program, close the putty window.

### Run the Program

Step 1:





Step 2:

Give IP address as 172.24.73.80 and port no. as 22

On the left panel,


Connection → SSH → X11 → Enable X11 forwarding



### Step 3:

After logging in with your credentials, enter

\$ dosbox




```
172.24.73.80 - PuTTY
login as: 1610501001
1610501001@172.24.73.80's password:
Access denied
1610501001@172.24.73.80's password:
Welcome to Ubuntu 16.04.5 LTS (GNU/Linux 4.7.0.intel.rs.0 x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/advantage

7 packages can be updated.
5 updates are security updates.

Last login: Tue Aug  7 11:26:54 2018 from 172.24.73.191
$ dosbox
```

After this, you will be greeted with DOSBOX prompt



```
DOSBox 0.74, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX

Welcome to DOSBox v0.74

For a short introduction for new users type: INTRO
For supported shell commands type: HELP

To adjust the emulated CPU speed, use ctrl-F11 and ctrl-F12.
To activate the keymapper ctrl-F1.
For more information read the README file in the DOSBox directory.

HAVE FUN!
The DOSBox Team http://www.dosbox.com


Z:\>SET BLASTER=A220 I7 D1 H5 T6
Z:\>
```

### Step 4:

In DOSBOX prompt, enter

Z:\> mount c: /home/your\_roll\_no/masm

Z:\> c:



```
DOSBox 0.74, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX

Welcome to DOSBox v0.74

For a short introduction for new users type: INTRO
For supported shell commands type: HELP

To adjust the emulated CPU speed, use ctrl-F11 and ctrl-F12.
To activate the keymapper ctrl-F1.
For more information read the README file in the DOSBox directory.

HAVE FUN!
The DOSBox Team http://www.dosbox.com

Z:\>SET BLASTER=A220 I7 D1 H5 T6

Z:\>mount c: /home/1610501001/masm
Drive C is mounted as local directory /home/1610501001/masm/

Z:\>c:

C:\>_
```

Step 5:

Run the program, with MASM specific commands.