




 ROUTER

```
ROUTER#enable
ROUTER#config t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#interface ethernet0/0
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Jul 18 05:31:46.970: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#config t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#username asraf password 9393
ROUTER(config)#line console 0
ROUTER(config-line)#password 9393
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)# line vty 04
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password 9393
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
*Jul 18 05:37:03.211: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
ROUTER#
```

QEMU (Win)

Administrator: Command Prompt

Microsoft Windows [Version 6.1.7601]

Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\user>ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Reply from 50.0.0.1: bytes=32 time<1ms TTL=255

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\Users\user>



50.0.0.1 - PuTTY

User Access Verification

Password:

ROUTER>enable

Password:

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#