CLOUD4C



# UCP Manual for Linux + MiddleWare

CLOUD4C SERVICES PVT LTD



## **Document control**

## **Prepared By**

Version	Author	Date
V 1.0	Sai Krishna	29-04-2022

## **Reviewed By**

Version	Reviewer	Date
V 1.0	Priyadarshi Mishra	30-04-2022

## **Approved By**

Version	Approver	Date
V 1.0	Harmandeep Singh	30-04-2022

## **Change Control**

Version	Change Reason	Effective Date
V 1.0	Initial Release	

#### STATEMENT OF CONFIDENTIALITY

This document contains proprietary trade secret and confidential information to be used solely for evaluating CtrIS & Cloud4C Datacentres' Ltd. The information contained herein is to be considered confidential. Customer, by receiving this document, agrees that neither this document nor the information disclosed herein, nor any part thereof, shall be reproduced or transferred to other documents, or used or disclosed to others for any purpose except as specifically authorized in writing by Ctrl S Datacentres' Ltd.



### Contents Document control\_\_\_\_\_\_2 Prepared By \_\_\_\_\_ \_\_\_2 Reviewed By \_\_\_\_\_ 2 Approved By \_\_\_\_\_\_ Change Control \_\_\_\_\_\_\_2 STATEMENT OF CONFIDENTIALITY \_\_\_\_\_ 2 Contents \_\_\_\_\_ 1. Introduction to UCP\_\_\_\_ 4 2. Procedure \_\_\_\_\_\_ 4 3. Glossary\_\_\_\_\_ 20 3.1 Definition \_\_\_\_\_\_\_20



## 1. Introduction to UCP

Welcome to UCP User guide.

This document helps users to provision different types of Linux Machines, namely the following

- a. Plain Linux Images
- b. Apache HTTPD Linux Images
- c. Apache TOMCAT Linux Images
- d. JBOSS Linux Images

In addition this document also emphasizes on various features such as


- a. Mountpoints
- b. Additional Disk requests while raising a service order
- c. Provisioning in desired zones
- d. Provisioning with desired availability sets
- e. Cloning of Machines

## 2. Procedure

- Step 1 Login to UCP
- Step 2 Navigate to the Service Order by Clicking on Order -> New VM Instance -> Azure
- Step 3 Service Order Page appears as below


In Basic Info Page please select the Following details

- a. For Production servers please select ITS-SPCS-Azure-Managed-VM-PROD-122
- b. For Test servers please select ITS-SPCS-Azure-Managed-VM-PROD-123




- c. VM Resource group automatically populates to the one that you're assigned to, otherwise you may click on the drop-down option to select relevant Resource Group.
- d. Gallery Name is automatically set to sig dhl iaas images. This cannot be modified.
- e. Servers can be provisioned based on two types of Operating Systems
  - a. Linux
  - b. Windows







f. Selecting Linux Will show the Add-Ons as below.



g. Selecting relevant Add-on will then filter to the related images with which servers can be provisioned. For example this is how a Plain Linux template can be selected.




h. After selecting the desired image the latest version of the image will automatically appear.




i. The Environment is by default selected to Production for ITS-SPCS-Azure-Managed-VM-PROD-122 and as TEST for ITS-SPCS-Azure-Managed-VM-TEST-123






- j. Selection either one of the options for Classified or Unclassified Networks.
  - a. Servers provisioned in Classified Network have access to the internet
  - b. Whereas Server provisioned in Unclassified Network do not have access to the internet.



- k. Network Resource Group is set to Default.
- I. Please select desired Region. The selected region is the datacenter where the requested server will be provisioned.



m. Automatically the relevant Virtual Network is selected along with the subnet.










- n. Select the number of servers that need to be provisioned in a single order.
  - a. At a time, a maximum of 10 similar servers can be ordered & provisioned.
  - b. Note: These servers will have exactly the same base machine or SKU. This will be explained in the following steps



- o. Cluster option will be explained in the user guide for Cluster Servers.
- p. For every order either a Availability Zone / Availability Set / None option can be selected.




q. After selected all the relevant options please click on Next on the bottom Right of the screen.




**Step 4** – The next page allows the user to select the Base Machine details.






- a. Select the desired server size by clicking on "Select VM Size" which will then show the list of VM sizes available for the relevant image.
  - a. Note: For each image of Linux & Windows only the supported list of VM SKUs will appear.



- b. Select the desired VM size and click on the SAVE button.
- c. The user may also be able to change the server size by clicking on "Change VM Size" button.
- d. Selected the desired Operating System Storage Type from the list shown below.






- e. The Network details & NIC information is automatically populated and cannot be modified.
- f. However, a relevant zone can be selected based on previous selection in Step-3.p




- g. User may choose to add Additional disks if required. This is possible by clicking on Add Disks button.
  - a. Note: The number of maximum disks that can be added is pre-defined by the Size of the base machined that has been selected in Step-4.a.a
  - b. In the below mentioned example a server size is selected where it can support only 2 additional disks
  - c. The additional disks can also be selected based on its disk types & sizes available.



d. Disk Storage SKU1 dropdown option will provide the list of supported disk types along with the size of the disk






e. After selecting relevant disk type & size, Disk Host caching can be selected based on the options available




- f. Mount-points to each disk can be defined by clicking on Add Mount-points button.
  - Note: As many mount-points as possible can be defined in this section, however the sum of all partitions of the mount-points cannot be exceed 5GB less of Disk Size.
     Meaning if a 32GB disk is selected, the sum of all partitions cannot be greater than 27 GB.



i. A mountpoint needs to be defined with a "/" and the label name will be automatically populate for every mount point as per the format mentioned in the text box.






g. After configuring the desired option, click next on the bottom right to select Backup related information and Global Service Now Details for Business purposes



- h. Or Click on Back to go to the previous page for changes in Basic Information.
- i. The final page for adding the service to cart is the Backup & GSN information screen




- j. All the options to enable backup for the desired server are auto-populated and pre-selected.
  - i. Note: For every production server the Backup policy is selected as GOLD
  - ii. For every test server the Backup Policy is selected as BRONZE.
  - iii. The details of these policies will be shared in the FAQ section







- k. For Global Service Now Business details the Following options can be selected
  - i. IMPACT



ii. Impacted BUSINESS UNIT



iii. Impacted COUNTRY.




- iv. Impacted region is automatically selected based on the Impacted Country.
  - 1. Note: Multiple Countries & Regions can be selected based on the business requirements.
  - 2. Note: Selecting multiple Countries will auto select regions and vice-versa.






v. Impacted service can be selected based on the list of 4000+ services available.



I. After having selected all the relevant information click on the "Add to Cart" button to place the order for the service.



**Step 5** – user will be navigated to Order List screen for approving the provisioning.


Note: If the user requesting for the server is a Team Member then the Resource Group Owner alone can approve or reject the Order request.

Note: if the user requesting for the server is a Team Manager then he/she can approve or reject the order request.


After approving the request the Resource Group Owner/ Team Manager should click on Submit to Order the server for Provisioning.

Note: Until the Submit button is clicked, the Order will not be sent for Provisioning.






After clicking on Submit Button the preview of the Order is shown in the next screen.




The Team Manager or Resource Group Owner only can click on Proceed to Provisioning button to order the server.




Once the desired server is sent to provisioning the following acknowledgement screen will appear, along with an acknowledgement email.







**Step 6** – To Check for Provisioning Status Navigate to Order -> Deployment Information.



a. There are several tabs to check for the status of activities performed in UCP. The table mentioned hereunder outlines all the activities.



Sl.No	Main Tab	Sub-Tab	Acitivit	TV .
1.	TVIGITI TOD	IAAS Linux	i.	Plain Linux Machines <b>with</b> Additional Disk
2		IAAS Linux DB	i.	Oracle Machines with Additional Disk
_		IAAS LIIIUX DB	ii.	TOMCAT Machines with Additional Disk
			iii.	APACHE Machines with Additional Disk
2		Lieuw Mahlagia	iv.	JBOSS Machines with Additional Disk
3. 4.		Linux WebLogic	i.	WebLogic Machines with Additional Disk
4.		IAAS Linux Cluster	i. ::	SAP Veritas Clusters with Additional Disk
-		IAAC Limuu \A/ithaut	ii.	Veritas Clusters with Additional Disk
5	Linux Provisioning	IAAS Linux Without Disk	i.	Plain Linux Machines <b>without</b> Additional Disk
6		IAAS Linux DB	i.	Oracle Machines without Additional Disk
В		Without Disk		
		Without Disk	ii. 	TOMCAT Machines without Additional Disk
			iii.	APACHE Machines without Additional Disk
			iv.	JBOSS Machines <b>without</b> Additional Disk
7		IAAS Linux Cluster	i.	SAP Veritas Clusters <b>without</b> Additional Disk
•		Without Disk	ii.	Veritas Clusters <b>without</b> Additional Disk
		.,	11.	Terras clasters tritilout Additional Disk
8		IAAS Windows	i.	Plain Windows with Additional Disk
			ii.	Windows IIS with Additional Disk
9	Windows	IAAS Windows DB	i.	Windows MSSQL with Additional Disk
10	Provisioning	IAAS Windows	i.	Plain Windows without Additional Disk
	FIOVISIOIIIII	without Disk	ii.	Windows IIS without Additional Disk
11		IAAS Windows DB	i.	Windows MSSQL without Additional Disk
		without Disk		
12		IAAS Linux	i.	Plain Linux Machines <b>with</b> Additional Disk
		Decommissioning		
13		IAAS Linux DB	i.	Oracle Machines with Additional Disk
		Decommissioning	ii.	TOMCAT Machines with Additional Disk
			iii.	APACHE Machines <b>with</b> Additional Disk
			iv.	JBOSS Machines <b>with</b> Additional Disk
14		Linux WebLogic	i.	WebLogic Machines <b>with</b> Additional Disk
		Decommissioning		
15		IAAS Linux Cluster	i.	SAP Veritas Clusters <b>with</b> Additional Disk
	Linux	Decommissioning	ii.	Veritas Clusters with Additional Disk
16	Decommissioning	IAAS Linux Without	i.	Plain Linux Machines <b>without</b> Additional Disk
		Disk Decommissioning		
17		IAAS Linux DB	i.	Oracle Machines <b>without</b> Additional Disk
		Without Disk	ii.	TOMCAT Machines without Additional Disk
		Decommissioning	iii.	APACHE Machines without Additional Disk
			iv.	JBOSS Machines <b>without</b> Additional Disk
10		IAAS Linux Cluster	:	SAP Veritas Clusters <b>without</b> Additional Disk
18		Without Disk	i. ::	
			ii.	Veritas Clusters <b>without</b> Additional Disk
19		Decommissioning IAAS Windows	i.	Plain Windows with Additional Disk
19	Windows		i. ii.	Windows IIS with Additional Disk
20		Decommissioning IAAS Windows DB	i.	Windows MSSQL with Additional Disk
20	Decommissioning		1.	williauws wissql with Additional DISK
		Decommissioning		



IAAS Windows without Disk without Disk Decommissioning IAAS Windows DB without Disk Decommissioning  IAAS Windows DB without Disk Decommissioning  Windows MSSQL without Additional Disk without Disk Decommissioning  Windows User On- Onboard a user to a Windows Plain or IIS machi	
Decommissioning  IAAS Windows DB without Disk Decommissioning  i. Windows MSSQL without Additional Dis	
IAAS Windows DB i. Windows MSSQL without Additional Diswithout Disk Decommissioning	
without Disk Decommissioning	
Decommissioning	k
Windows User On- Onboard a user to a Windows Plain or US machi	
vviildows osci on   Olibodia a asci to a vviildows Halli of ils illacili	ne as
boarding either	
i. Administrator or	
ii. Remote Desktop User	
24 Windows User Off- Offboard a user from a Windows Plain or IIS Ma	chine
boarding either as	
i. Administrator or	
ii. Remote Desktop User	
25 Windows SQL user Onboard a Database user onto MSSQL DB as	
On-boarding a. User Account	
User On-boarding i. MSSQL Reader	
ii. MSSQL DataReader	
iii. MSSQL DataWriter	
iv. MSSQL AgentReader	
v. MSSQL DBSSISAdmin	
AD User Onboarding Onboard a abc@dhl.com email id user to	
(Active Directory) i. UDLDHL-UCP (UCP Access)	
ii. UDLDHL-PVWA (Cyberark Platform Acce	s)
AD User Off-boarding Offboard a abc@dhl.com email id user from	
(Active Directory) i. UDLDHL-UCP (UCP Access)	
ii. UDLDHL-PVWA (Cyberark Platform Acce	s)
28 Windows SQL Service Onboard a Database user onto MSSQL DB as	
Account Onboarding a. Service Account	
i. MSSQL DBOwner	
ii. MSSQL SysAdmin	
iii. MSSQL AgentReader	
iv. MSSQL DBSSISAdmin	
W. Wissqt BBssis/turiiii	
29 IAAS Windows OAT Status of OAT Checklist Re-Run for Windows Pla	in & IIS
Rerun Machines	
30 IAAS Linux OAT Rerun Status of OAT Checklist Re-Run for any Plain Lin	xr
Machine Machine	
Other Jobs IAAS-Linux DB OAT Status of OAT Checklist Re-Run for all	
Rerun i. Oracle Machines	
ii. Tomcat Machines	
iii. Apache Machines	
iv. JBOSS Machines	
32 IAAS-Linux Weblogic Status of OAT Checklist Re-Run for all	
OAT Rerun i. Weblogic Machines	
33 IAAS-Linux Cluster Status of OAT Checklist Re-Run for all	
OAT Re-Run i. SAP Veritas Cluster Machines	
ii. Vertias Cluster Machines	
34 IAAS-Windows SQL Status of OAT Checklist Re-Run for all	
OAT Re-Run i. MSSQL Machines	



35	IAAS Linux DB Add	Provisioning of Additional Disk for already provisioned
	Disk	i. Oracle Machines
		ii. Tomcat Machines
		iii. Apache Machines
		iv. JBOSS Machines
36	IAAS Linux Weblogic	Provisioning of Additional Disk for already provisioned
	Add Disk	i. Weblogic Machines
37	IAAS Windows DB Ac	d Provisioning of Additional Disk for already provisioned
	Disk	i. MSSQL Machines

### b. Status of Provisioning – There are 3 Statuses

Provisioning	IN-PROGRESS	Provisioning of a server is In-Progress
	SUCCESS	Provisioning of a server is Successful
	FAILURE	Provisioning of a server has Failed


#### c. Status of Resizing – There are 3 Statuses

Resizing	IN-PROGRESS	Resizing of a server is In-Progress	
	SUCCESS	Resizing of a server is Successful	
FAILURE		Resizing of a server has Failed	

### d. Status of Decommissioning – There are 3 Statuses


D.	Decommissioning	1. IN-	2.	Decommissioning of a server is In-Progress
		PROGRESS		
В.		4. SUCCESS	5.	Decommissioning of a server is Successful
5.		7. FAILURE	В.	Decommissioning of a server has Failed

**Step 7** – To view the successfully provisioned server Navigate to Manage -> Azure -> VM List




a. Either select by the filtering options available or Enter the hostname of the server.





b. Click on VM Details Button to view the details of the server that has been provisioned.







# 3. Glossary

## 3.1 **Definition**

Terms	Abbreviation
VM	Virtual Macine
UCP	Universal Cloud Platform