Mesh to Terrain

Version 1.6



Infinity Code, 2013-2015

http://www.infinity-code.com/

Description

Component to convert 3D models into Unity Terrain. Can work as with all objects on a layer, and only the selected objects. Does not require the addition of the components of physics.

Using

Add the 3D scene model that you want to convert into Terrain. The number of models is not limited, and they can have any nesting.

Select the menu item **«Window / Infinity Code / Mesh to Terrain»**, to open the component.

Window component consists of three sections:

- Meshes Configuration models, which will be converted into terrains.
- **Terrains** List of terrains.
- **Textures** Settings texture generation.

In **«Mesh select type»** section Meshes, select how you want to define a model for the transformation:

- GameObjects Objects to be added manually. For all the added objects considered subobjects.
 To avoid errors, you must remove all unnecessary sub-objects of the objects do not belong to the terrain.
- Layers As models for the conversion of all the models used in the layer. In order to avoid errors from the layer to remove all unnecessary objects that do not belong to the terrain.

In «Direction», specify the direction of raytracing:

- Normal The Rays go from the top down.
- Reversed The Rays are bottom-up. Must be used if the polygon model is facing downwards.

In **Y Range**», select the desired range of heights. The higher the value, the lower the accuracy.

- Minimal Range the range of values will be determined automatically based on the meshes.
- Long Mesh Side the range of values will be determined by the maximum size of X and Z.
- Fixed Value allows you to specify a Y range manually.

In «Type» section Terrains, select:

- Exist Terrains If you want to convert your existing terrains. To do this, place the terrains under the models and add terrains to the list.
- **New Terrains** Terrains will be created and placed under the model automatically. In the appropriate fields number of the terrains that will be created.

If in **«Type»** section Terrains selected **«New Terrains»**, then there are additional settings:

- Count Number of terrains you want to get.
- **Bounds** Type boundary of the model. The options are determined automatically or set another GameObject. GameObject borders should be Cube without rotation and include the entire area you want to convert.
- New terrains settings.

If you want to use smoothing, choose the **«Use smoothing of height maps»** and set the smoothing factor.

In the field «Type» section Textures, select:

- **No Texture** Texture for terrains not be created.
- Bake Main Textures For each terrain creates a separate texture, the size specified. If in a certain place of the components can not get the main texture of the model, it will be replaced by the color specified in the **«Empty color»**.

Press the **«Start»** and wait for the conversion. Depending on your computer system, the number of places and settings it can take from a few seconds to several minutes.

Important. If the model is added collider, other than **«Mesh Collider»**, it can be properly processed. To solve the problem, remove the component model collider.

Working with Relief Terrain Pack

Relief Terrain Pack is not included with Mesh to Terrain package and by default its support is disabled.

Import Relief Terrain Pack to your project. Open Mesh to Terrain. Third-party / Enable Relief Terrain Pack.

No settings Relief Terrain Pack is required. If you have any questions about Relief Terrain Pack, you can find answers in the documentation of Relief Terrain Pack.

If you want to delete Relief Terrain Pack from the project, you should disconnect it in Mesh to Terrain (Third-party / Disable Relief Terrain Pack).

If you forget to disable Relief Terrain Pack and removed it, then you will see errors in the console. To manually remove support Relief Terrain Pack, open PlayerSettings (Edit / Project Settings / Player) and delete the corresponding entry from the «Scripting Define Symbols».

Updating versions

In Unity Asset Store we ship only stable versions. Renewal period is several months.

Mesh to Terrain has a built-in update system, using which you can get early access to all versions and updates.

Click **«Window / Infinity Code / Mesh to Terrain / Check Updates»**, to open window checking for updates. Enter your Invoice Number, select a channel of updates and click **«Check New Versions»**.

If updates are available, you can read the list of changes and download the update.

If you have any problems with installing the update, then:

- 1. Open an empty scene.
- 2. Delete the folder «Infinity Code / Mesh to Terrain».
- 3. Import the new asset version in the project.

Troubleshooting

After starting you get the error border or nothing happens.

There are two reasons for this:

- 1. The models in the scene have a size that is insufficient for correct operation of physics. You need to increase the model in 100 + times and start the component again The problem is that the default scaling factor of imported models **«0.01»**.
- 2. You choose the models are not in the scene. Add model in the scene and convert them.

Terrains not correspond to the models axis Y.

1. Scale up the model several times.

New terrains have a insufficient resolution / accuracy.

- 1. Increase the Height Map Resolution.
- 2. Increase the number of new terrains.

You can not see the grass or trees.

- 1. Zoom in to the place where you draw grass or trees.
- 2. Increase the value of «Tree Distance» in Terrain settings.

You receive an error «Selected meshes not in the scene», and the model is in the scene.

Please make sure that you choose a model from the tab «Scene».

Links

Product page: http://infinity-code.com/en/products/mesh-to-terrain

Support: support@infinity-code.com