

Module – 15

FSMO –A domain wide roles



Domain Wide Roles - FSMO

1. RID
2. PDC
3. Infrastructure



RID (Relative Identifier)

- » Every object identify by **SID** (**Security Identifier**) number.
- » Active directory also know object by SID numbers.
- » SID number consist of **Unique domain number** and **RID number**.
- » Whenever object is created in domain a **Unique SID** is assign to that object.



RID (Relative Identifier)

» **SID = Domain number + RID number**

» **Domain Number:** Domain number uniquely identifies the domain, this number is fixed for all objects created in domain.

» **RID Number:** RID master is give RID number to each object. RID number is unique for every objects in domain.

» RID master in it lifespan can issue over 1 billion unique SID.

» Its also issue RID pool in increment of 500 to the other DC in same

domain.

www.yoinsights.com



RID (Relative Identifier)

- » dcdiag /v /test:ridmanager
- » Transfer the roles to DC to ADC
- » dsa.msc



Infrastructure Master

- » The infrastructure master roles domain controller maintain consistency of object during inter domain operation
- » Like when user in one domain needed to another domain



PDC Master

- » Password changes on any DC are first updated to PDC and PDC will update to all other domain
- » Account locked in domain is also handled by PDC master
- » PDC act as time source to all domain controller of the domain (PDC may refer to local time/bios time or NTP server)
- » GP change only possible via PDC master



Overview:

- » If schema Master fails we cannot add new object/attributes in forest
- » If domain master fails, we cannot add or delete new domain in forest
- » If RID master fails new object can not be created in domain (after existing pool expires of ADC)
- » If infra master fails, movement of object fails between domain
- » If PDC master fails password change/account locked out/group policy/ time syn cannot be reflected in domain.



Seize:

- » Seize of FSMO roles only can perform when DC is down. When DC live only transfer can be done.
- » Once seize performed, you cannot directly up the DC. You have to Disconnect from network, replace the motherboard, format the DC and need to install fresh server OS.
- » Meta-clean up required (to remove DC entry)



Seize:

- » Syntax: On Domain controller that have FSMO role currently;
- » ntdsutil
- » Roles
- » Connections
- » Connect to server dc (Hostname current domain controller)
- » Ctrl Z
- » Seize PDC/RID/Infra/Schema/DNM