



2026 R1

© 2026 Synopsys, Inc and/or ANSYS, Inc. All rights reserved.
Unauthorized use, distribution, or duplication is prohibited.

Ansys Quick Start Licensing Guide



Release 2026 R1
000404

ANSYS, Inc. and
ANSYS Europe,
Ltd. are UL
registered ISO
9001:2015
companies.

License file and license manager installation made easy.

Copyright © 2026 Synopsys, Inc. and ANSYS, Inc. This Synopsys product and all associated documentation are proprietary to ANSYS, Inc. and Synopsys, Inc. and may only be used pursuant to the terms and conditions of a written license agreement. All other use, reproduction, modification or distribution of the Synopsys product or the associated documentation is strictly prohibited.

Table of Contents

..... 1

Migrating to the Ansys License Manager

The information in this guide applies only to the Ansys License Manager, and the tools that we provide to manage it (**Ansys License Management Center**).

Important Notices

The Ansys License Manager and its associated processes have been updated at Release 2026 R1; carefully review the *Ansys Licensing Guide* for more information on these updates. Because of these updates, you must upgrade to the Release 2026 R1 License Manager in order to run Ansys 2026 R1 products. The 2026 R1 Ansys License Manager supports prior Ansys releases, so upgrading the license manager will not cause problems for prior releases.

The instructions provided in this document assume that you will be managing your licensing environment using the tools we provide (**Ansys License Management Center**). If you will be using your own established processes to manage your licensing environment, the instructions provided here may not apply. Thoroughly review the *Ansys Licensing Guide* to understand the changes, and then refer to the section titled *Advanced Licensing Configuration Options* for detailed instructions.

Overview

The intent of this Quick Start Licensing Guide is to give you a simple overview of the steps required to install the 2026 R1 Ansys License Manager and license keys on a license server machine.

The term Ansys 2026 R1 is used throughout this guide to refer to all Ansys 2026 R1 products.

To install Ansys 2026 R1 and the client licensing, follow the instructions in the *Ansys, Inc. Installation Guide* for your platform.

If you are installing in a three-license server environment, the procedures below must be performed on all three license servers.

I. I am an existing customer with an existing valid license file. How do I proceed?

If you are an existing customer with a valid license file, you will not receive a new one until your existing license file expires. When you are ready to install the Ansys 2026 R1 package, follow the steps below:

1. Install Ansys 2026 R1 products following the instructions in the *Ansys Installation Guide* for your platform. The product installation includes the client licensing.

Note:

As of release 2024 R2, the license manager installation has been removed from the Ansys Product Installation package. To get the license manager installation, log on to the **Ansys Customer Portal** and download the Ansys License Manager Installation package from **Downloads>Current Release>Tools>Ansys License Manager**.

-
2. **Windows:**After downloading and extracting the License Manager Installaton package, right-click **setup.exe** and select **Run as Administrator**. When the installation launcher appears, click the **Install Ansys License Manager** option.

Linux:After downloading and extracting the License Manager Installaton package,, start the installation launcher by typing **./INSTALL -LM**.

3. The installation displays your current installation location.
4. When the installation is finished, the **Ansys License Management Center** opens in your default browser. If you have a new license file you wish to add, click the **Add A License File** option and add the appropriate file.

You are now ready to run Ansys 2026 R1 products.

II. I am a new customer and did not receive a license file with my Ansys 2026 R1 package.

If you are a new customer, or you are an existing customer using the Ansys license manager for the first time with your product(s), and you did NOT receive a license file with your Ansys 2026 R1 package, follow the steps below:

1. Install Ansys 2026 R1 products following the instructions in the *Ansys Installation Guide* for your platform. The product installation includes the client licensing.

Note:

As of release 2024 R2, the license manager installation has been removed from the Ansys Product Installation package. To get the license manager installation, log on to the **Ansys Customer Portal** and download the Ansys License Manager Installation package from **Downloads>Current Release>Tools>Ansys License Manager**.

2. **Windows:**After downloading and extracting the License Manager Installaton package, right-click **setup.exe** and select **Run as Administrator**. When the installation launcher appears, click the **Install Ansys License Manager** option.

Linux:After downloading and extracting the License Manager Installaton package,, start the installation launcher by typing **./INSTALL -LM**.

3. Follow the on-screen instructions to specify the installation location. We recommend accepting the default location. The default location for Windows machines is C: \Program Files\ANSYS Inc and the default location for Linux machines is /ansys_inc.
4. When the installation is finished, the **Ansys License Management Center** opens in your default browser. The first step to get a license file is to click the **Get System Hostid Information** option to display your hostid code(s).
5. Select the hostid you wish to use and click **SAVE TO FILE**.

A text file containing your hostid information is created.

-
6. Forward this text file to your Ansys sales representative so that a license file can be created for you.
 7. When you receive a license file from Ansys, Inc., save the file to a temporary directory.
 8. Open the **Ansys License Management Center**. For Windows, click **Start>All Programs>Ansys, Inc. License Manager>Ansys License Management Center** and for Linux run the `/shared_files/licensing/start_lmcenter` script.
 9. Click the **Add A License File** option.
 10. Browse to the temporary directory, select the license file and click **Open**.

The **Start License Manager** window is displayed, informing you that the License Manager will be started when you upload the license file.

11. Click **Install License File** to upload the license file and start the license manager.

The **Status** pane displays a message informing you whether the license manager started successfully or if any errors have been encountered.

You are now ready to run Ansys 2026 R1 products.

III. I am a new or existing customer and I received a license file with my Ansys 2026 R1 package.

If you are a new or existing customer, and you DID receive a license file with your Ansys 2026 R1 package, follow the steps below:

1. Save the license file that you received with your Ansys 2026 R1 package to a temporary directory.
2. Install Ansys 2026 R1 products following the instructions in the *Ansys Installation Guide* for your platform. The product installation includes the client licensing.

Note:

As of release 2024 R2, the license manager installation has been removed from the Ansys Product Installation package. To get the license manager installation, log on to the **Ansys Customer Portal** and download the Ansys License Manager Installation package from **Downloads>Current Release>Tools>Ansys License Manager**.

3. **Windows:**After downloading and extracting the License Manager Installation package, right-click **setup.exe** and select **Run as Administrator**. When the installation launcher appears, click the **Install Ansys License Manager** option.

Linux:After downloading and extracting the License Manager Installation package,, start the installation launcher by typing **./INSTALL -LM**.

4. Follow the on-screen instructions to specify the installation location. We recommend accepting the default location. For existing customers, this will install over the existing release. The default

location for Windows machines is C:\Program Files\Ansys Inc and the default location for Linux machines is /ansys_inc.

5. When the installation is finished, the **Ansys License Management Center** opens in your default browser.
6. Click the **Add A License File** option.
7. Browse to the temporary directory, select the license file and click **Open**.

The **Start License Manager** window is displayed, informing you that the License Manager will be started when you upload the license file.

8. Click **Install License File** to upload the license file and start the license manager.

The **Status** pane displays a message informing you whether the license manager started successfully or if any errors have been encountered.

You are now ready to run Ansys 2026 R1 products.

IV. Finding more information

For more information on installing Ansys 2026 R1 and setting up the licensing, you can refer to the following documents:

Ansys Licensing Guide

Ansys Installation Guide for Windows

Ansys Installation Guide for Linux

See the "Troubleshooting" section of the *Ansys Licensing Guide* if you encounter any problems or error messages.