E

Accept Agreement:

Select storage :

VMware ESXi 6.7.0 Installer

```
              Please select a keyboard layout
 Swiss French
 Swiss German
 Turkish
 US Default
 US Dvorak
 Ukrainian
 United Kingdom

           Use the arrow keys to scroll.

 (Esc) Cancel      (F9) Back      (Enter) Continue
```

Select Keyboard Layout :

VMware ESXi 6.7.0 Installer

```
              Enter a root password

  Root password:
 Confirm password:
              Please enter a password.

 (Esc) Cancel      (F9) Back      (Enter) Continue
```

Set NodeESXi Root Password :

VMware ESXi 6.7.0 Installer

```
                 Confirm Install

 The installer is configured to install ESXi 6.7.0 on:
        naa.600508e0000000003b663aea39bb3705.

      Warning! This disk will be repartitioned.

 (Esc) Cancel      (F9) Back      (F11) Install
```

Installation complete (Reboot)CLII interface to configuration

```
System Customization                          Configure Password

Configure Password                            Set
Configure Lockdown Mode
                                              To prevent unauthorized access to this system, set the
Configure Management Network                  password for the user.
Restart Management Network
Test Management Network
Network Restore Options

Configure Keyboard
Troubleshooting Options

View System Logs

View Support Information

Reset System Configuration
```

CLI Interface to Configuration:

```
Configure Management Network                  IPv4 Configuration

Network Adapters                              Automatic
VLAN (optional)
                                              IPv4 Address: 169.254.157.31
IPv4 Configuration                            Subnet Mask: 255.255.0.0
IPv6 Configuration                            Default Gateway: Not set
DNS Configuration
Custom DNS Suffixes                           This host can obtain an IPv4 address and other networking
                                              parameters automatically if your network includes a DHCP
                                              server. If not, ask your network administrator for the
                                              appropriate settings.
```

Configure Management Network

```
Configure Management Network                  IPv4 Configuration

Network Adapters                              Manual
VLAN (optional)
                                              IPv4 Address: 109.203.103.124
IPv4 Configuration                            Subnet Mask: 255.255.255.0
IPv6 Configuration                            Default Gateway: 109.203.103.1
DNS Configuration
Custom DNS Suffixes                           This host can obtain an IPv4 address and other networking
                                              parameters automatically if your network includes a DHCP
                                              server. If not, ask your network administrator for the
                                              appropriate settings.

        IPv4 Configuration

        This host can obtain network settings automatically if your network
        includes a DHCP server. If it does not, the following settings must be
        specified:

        ( ) Disable IPv4 configuration for management network
        ( ) Use dynamic IPv4 address and network configuration
        (o) Set static IPv4 address and network configuration:

        IPv4 Address                                  [ 109.203.103.124 ]
        Subnet Mask                                   [ 255.255.255.0   ]
        Default Gateway                               [ 109.203.103.1   ]

        <Up/Down> Select  <Space> Mark Selected          <Enter> OK  <Esc> Cancel
```

Set IPV4


```
Configure Management Network                    DNS Configuration

Network Adapters                      Manual
VLAN (optional)
                                      Primary DNS Server:
IPv4 Configuration                    8.8.8.8
IPv6 Configuration                    Alternate DNS Server:
DNS Configuration                     1.1.1.1
Custom DNS Suffixes
                                      Hostname
                                      localhost

                                      If this host is configured using DHCP, DNS server addresses
          ┌────────────────────────────────────────────ned automatically. If
          │ DNS Configuration                          or the appropriate
          │ This host can only obtain DNS settings automatically if it also obtains
          │ its IP configuration automatically.
          │
          │ ( ) Obtain DNS server addresses and a hostname automatically
          │ (o) Use the following DNS server addresses and hostname:
          │
          │ Primary DNS Server      [ 8.8.8.8                            ]
          │ Alternate DNS Server    [ 1.1.1.1                            ]
          │ Hostname                [ localhost                          ]
          │
          │ <Up/Down> Select  <Space> Mark Selected      <Enter> OK  <Esc> Cancel
          └────────────────────────────────────────────────────────────────┘
```

Set DNSeriver :

Restart Management Network


```
System Customization                  Restart Management Network

Configure Password                    Restarting the management network interface may be required
Configure Lockdown Mode               to restore networking or to renew a DHCP lease.

Configure Management Network          Restarting the management network will result in a brief
Restart Management Network            network outage that may temporarily affect running virtual
Test Management Network               machines.
Network Restore Options
                                      Note: If a renewed DHCP lease results in a new network
Configure Keyboard                    identity (e.g., IP address or hostname), remote management
Troubleshooting Options               software will be disconnected.

View System Logs

View Support Information

Reset System Configuration
```