

Set up your BeSe Tech email

Use your company mailbox in IONOS Webmail, Apple Mail on iPhone, or Microsoft Outlook. IMAP keeps your inbox, sent mail, and folders synchronized across devices.

Before you begin

Have your **full email address** (for example, name@besetech.ca) and your **mailbox password** ready.

Option 1 - IONOS Webmail

1. Open mail.ionos.ca in a web browser.
2. Sign in with your **full BeSe Tech email address** and mailbox password.
3. Your inbox is ready immediately. You can read, reply, organize folders, and send email from the browser.

Option 2 - iPhone Mail

1. Open **Settings > Apps > Mail > Mail Accounts > Add Account**.
2. Choose **Other > Add Mail Account**.
3. Enter your name, full email address, mailbox password, and a description such as BeSe Tech.
4. Choose **IMAP**.

Incoming Mail Server

Host: imap.ionos.com

Username: your full email address

Password: your mailbox password

Outgoing Mail Server

Host: smtp.ionos.com

Username: your full email address

Password: your mailbox password

5. Tap **Save**, open Mail, and send a test message.

Example configuration

IMAP

POP

Name	Your Name
Email	name@besetech.ca
Description	BeSe Tech

Incoming Mail Server

Host Name	imap.ionos.com
User Name	name@besetech.ca
Password	

Outgoing Mail Server

Host Name	smtp.ionos.com
User Name	name@besetech.ca
Password	

Security note

Never share your mailbox password in this guide, by regular email, or in a group chat. If a password must be issued, send it separately using an approved secure method.

Outlook and manual server settings

Outlook often detects IONOS automatically. Use the manual settings below only if automatic setup does not complete.

Option 3 - Microsoft Outlook

1. Open Outlook and select **Add Account**.
2. Enter your full BeSe Tech email address and continue.
3. If automatic setup fails, choose **Advanced options** or **IMAP**.
4. Enter the server settings below. Use your full email address as the username for both incoming and outgoing mail.
5. Make sure **Outgoing server requires authentication** is enabled, then finish setup.

Setting	Incoming mail	Outgoing mail
Protocol	IMAP	SMTP
Server	imap.ionos.com	smtp.ionos.com
Port	993	587
Security	SSL/TLS	STARTTLS
Username	Your full email address	Your full email address
Password	Your mailbox password	Your mailbox password

If sending fails Try SMTP port **465** with **SSL/TLS**. Confirm that SMTP authentication is enabled and that the username is your full email address.

Test your account

1. Send a message from your BeSe Tech address to an external address you can access.
2. Reply from the external address.
3. Confirm both messages appear in your email app and in IONOS Webmail.

Quick troubleshooting

Password rejected: Confirm you are using the mailbox password, not necessarily the main IONOS account password.

Messages do not synchronize: Confirm the account type is IMAP and the incoming port is 993 with SSL/TLS.

Can receive but not send: Check SMTP authentication, username, encryption, and port 587 or 465.

Need help? Contact info@besetech.ca. Include your device type and a short description of the issue, **but never include your password**.

Official IONOS Help resources: [Webmail login](#) and [email server settings](#).