

1. LOCATOR MAP

STING_TB_A1_v2.0 — A1 landscape working sheet

1

STATUS ■ SUITABILITY ■ ISSUE PURPOSE ■ FEDERATION ■ LOIN/LOD	
DRAWABLE ZONE (viewport area — scope-box / view crop / element-bbox)	LOGO BAND
	ORIGINATOR PRACTICE
	CLIENT / APPOINTING
	PROJECT
	COORD / NORTH / KEY
	NOTES + STATUTORY
	DRAWING TITLE
	ID — 7 SEGMENTS
	FULL SHEET REF
	SHEET-OF / SCALE / DATE
	AUTHORING (DR/CK/AP/AU)
	TR / CDE / MIDP
	QR + DISCLAIMER

REVISION HISTORY — Rev | Date | Description | Drwn | Chkd | Appr | Suit. | Stat.

16

15

LEGEND — field groups

- 1
- Top status band (5 chips)
- 2
- Originator + client logos
- 3
- Originator practice block
- 4
- Client + appointing party
- 5
- Project name + address + RIBA
- 6
- Coordinate sys + project north +
- 7
- Notes + CDM + copyright
- 8
- Drawing title (sheet name)
- 9
- ID seven-segment breakdown
- 10
- Full concatenated sheet ref
- 11
- Sheet-of-total + scale + date
- 12
- Authoring 4-eyes (DR/CK/AP/AU)
- 13
- TR-ref + CDE path + MIDP id
- 14
- QR code + disclaimer + print bar
- 15
- Revision history (8 cols)
- 16
- Print-scale check bar

2. A1 LANDSCAPE WORKING SHEET

STING_TB_A1_v2.0 — bottom-strip layout, BIM-mode toggle

DRAWABLE ZONE

830 × 480 mm (BIM mode on) 830 × 520 mm (BIM mode off)
DrawingType.Slots[] resolved by SheetTemplateEngine

■■■■ BIM ONLY (entire row hides when STING_BIM_MODE_BOOL = 0) ■■■■

TR-REF \${TRANSMITTAL_REF} CDE \${CDE_PATH} MIDP \${DELIVERABLE_ID} LOIN/LOD \${LOIN_LOD} FED \${FEDERATION_STATUS} [QR]

CLIENT

NOTES

DRAWING TITLE

DRAWING TITLE.

STATUS

SUITABILITY

REV

REV-DATE

DATE

PAPER SIZE

SCALE

DRWN

CHKD

APPR

AUTH

BIM ONLY — 7-SEGMENT ID

PRI STG ORG PLNS VOL ZZ LVL 01 TYPR DR ROL A SEQ 0001

DRG STATUS

DRG NO.

SHEET

DRG STATUS

DRG NO.

SHEET

DRG STATUS

DRG NO.

SHEET

REVISION HISTORY

REV

DATE

DESC.

DRWN

CHKD

APPR

SUIT.

STAT.

Bottom-strip layout — drawable area maximised. 12 BIM-only cells (highlighted amber) collapse when STING_BIM_MODE_BOOL = 0; strip auto-shortens from ~110 mm to ~70 mm.

3. A4 PORTRAIT WORKING SHEET

STING_TB_A4_PORT_v1.0 — bottom strip layout for RFI / memos / single-page schedules

STATUS #{STATUS}	SUITABILITY #{SUITABILITY}	REV #{REV}	DATE #{REV_DATE}		
DRAWABLE ZONE Single MAIN slot (0.0, 0.0, 1.0, 1.0)					
ORG LOGO #{ORG_NAME} #{ORG_ADDRESS}		CLIENT LOGO			
PROJECT #{PROJECT_NAME} #{PROJECT_ADDRESS} Project no. #{PROJECT_NUMBER} Client #{CLIENT_NAME} RIBA #{RIBA_STAGE} Coord #{COORD_SYS}					
DRAWING TITLE #{SHEET_NAME} PRJ #{PROJ} ORIG #{ORIG} VOL #{VOL} LVL #{LVL} TYPE #{TYPE} ROL #{ROL} SEQ #{SEQ} #{SHEET_FULL_REF}					
DRWN #{DR}	CHKD #{CK}	APPR #{AP}	AUTH #{AU}	REV #{REV}	OF #{OF_TOTAL}
TR #{TRANSMITTAL_REF} • CDE #{CDE_PATH} • MIDP #{DELIVERABLE_ID} Original A4 portrait					

Why bottom strip on portrait?

- A4 portrait is reserved for single-page deliverables — RFIs, technical queries, single-page schedules, transmittal memos.
- Right strip would consume too much of the 210 mm width — only ~140 mm of drawable zone remains. Bottom strip preserves the full 195 mm × 175 mm drawable area above.
- Status chips collapse to 4 (STATUS / SUITABILITY / REV / DATE) — full 5-chip band of A1 doesn't fit at 210 mm width.
- QR + revision-history strip moved to a continuation page when needed (SheetTemplateEngine handles overflow automatically).

Cell field count:

- 24 bound labels (vs 35 on A1 landscape)
- Same shared-parameter universe — TitleBlockParamApplier resolves identically.

Used by:

- Tags/RichTagDisplayCommands (RFI / clarification sketches)
- Planscape.Docs.Templates (transmittal cover letter, technical query, RFI, technical response, signature pages)
- Schedule sheets (door schedule, window schedule, finishes matrix at A4 portrait when small project)

Bound parameters specific to this family:

- STING_RFI_NR_TXT (when used as RFI)
- STING_RFI_SUBJECT_TXT
- STING_QUESTION_TEXT
- STING_RESPONSE_TEXT
- STING_RECIPIENT_NAME_TXT (transmittal use)
- STING_COST_IMPACT_TXT
- STING_TIME_IMPACT_TXT

4. A1 COVER PAGE

STING_TB_COVER_A1_v1.0 — issue bundle front sheet, no drawable viewport

22 bound cells. No viewport.

Generated by BIMManagerEngine.GenerateProjectCover.

ORIGINATOR LOGO
 \${ORG_LOGO}

CLIENT LOGO
 \${CL_LOGO}

`${PROJECT_NAME}`

`${PROJECT_ADDRESS}`

Project no. \${PROJECT_NUMBER} RIBA Stage \${RIBA_STAGE}

INFORMATION CONTAINER ISSUE

Suitability	\${SUITABILITY} — \${SUIT_DESC}
-------------	--

Issue purpose	<code>\${ISSUE_PURPOSE}</code>
---------------	--------------------------------

Revision **#{REV}**

Issue date	#{REV_DATE}
------------	--------------------

Transmittal	#{TRANSMITTAL_REF}
-------------	---------------------------

Deliverable	<code>\${DELIVERABLE_ID}</code>
-------------	---------------------------------

CDE container	<code>\${CDE_PATH}</code>
---------------	----------------------------------

LOIN / LOD	#{LOIN_LOD}
------------	--------------------

Originator \${ORG_NAME} (\${ORG_CODE})

Appointing party \${APPOINTING_PARTY}

Lead appointed party \${LEAD_APPOINTED_PARTY}

Statutory CDM / fire / asbestos as per individual sheets. \${COPYRIGHT} Original A1.


`#{SECURITY_CLASS}` — restricted distribution per CDE rules.

Sheet \${SHEET_FULL_REF} — Cover


{OF_TOTAL}

5. SLOT POSITIONS


DrawingType.Slots[] normalised over the drawable zone (top-left = 0,0 ; bottom-right = 1,1)




Default — used by presentation, cover, full-bleed sheets.




Plan + side detail / 3D — A1 working sheet default.




Elevations 4-up, render board, presentation context.




Riser diagrams, vertical sections.




Pipe / duct / conduit assembly. BOM strip on right (0.72...1.0).



Architectural plan with legend + key detail.



A3 landscape — left sketch, right RFI Q&A panel.




60 mm caption bar below render.

Coordinates are normalised to the drawable zone of the parent title block. SheetTemplateEngine resolves them to absolute mm at sheet creation time. Origin (0,0) = top-left of drawable zone.





Negative coords or coords > 1.0 spill outside the drawable zone — PlaceWithOverflowCommand handles overflow to continuation sheets.

6. MATCH-LINE DETAILS

Sheet-to-sheet continuation marks per BS 1192 §A.6



Two adjacent A1 sheets sharing a north–south match line. Symbol replicates on both sides; cross-reference back-links are auto-populated from STING_SHEET_FULL_REF on the paired sheet.



Match-line conventions:

- Drawn in the dedicated 'STING - Match Line' line style: red 0.50 mm projection, dashed-with-tick pattern.
- Each match line carries a label tag bound to STING_MATCH_REF_TXT — populated by the paired sheet's full ref.
- Use BS 1192 §A.6 placement: parallel to grid where possible, never through a sectioned element, never closer than 25 mm to drawable-zone edge.
- Pair detection: BatchSectionsCommand / GenerateFromScopeBoxesCommand auto-cross-references when two sheets share a scope box edge.
- Continuation arrow + 'see SHEET-REF' caption are detail-component placeholders; SheetTemplateEngine drops them at the line's tip.