

Mobile App Geofence Clocking Configuration Guide

PeopleXD Native App

Table of Contents

Document Control	4
1. Overview.....	5
1.1. Purpose of the Guide	5
1.2. What is Geofencing?.....	5
2. Configuration.....	7
2.1. How to access the Mobile App Clocking – Geofence Admin Screen.....	7
2.2. Create a Geofence	9
2.3. Manage Overrides	10
3. Manage a Geofence	11
3.1. Edit your Geofence.....	11
3.2. Assign Criteria Groups to your Geofence	11
3.2.1. Create a Criteria Group	12
3.2.2. Assign your Criteria Group(s) to your Geofence	12
3.2.3. Groupings	13
3.3. View Employee Assigned to your Geofence.....	13
3.4. Deactivate a Geofence.....	14
4. Geofencing Checklist	15
5. Manager Views	16
5.1. Time Exceptions	16
5.1.1. Manager Dashboard – Time Exception Widget.....	16
5.1.2. Workforce Management - Time Exceptions Screen	16
5.1.3. Time Exception View Map	17
5.2. Insight and Geofencing	17
6. Employee Views	19
6.1. Clocking In/Out.....	19
6.2. Using Location	19

Table of Contents

6.3.	Allowing Access to Device Location	20
6.4.	Returning User	20
6.5.	Dynamic Map.....	21
6.6.	Geofence - Historical Clockings.....	22
6.7.	Restriction Levels.....	22
6.8.	Employee Messages	23
7.	Menu Options	25
7.1.	Administrators Access	25
7.1.1.	Assign Geofence Clocking Admin Profile to Specific Admin Users	25
7.1.2.	Update an Existing Admin Menu Profile	25
7.2.	Employee Access	27
7.3.	Time Exceptions Access	27

Document Control

Version	Date	Author	Details
1.0	29/06/2021	Rory Coakley	Published to Access LMS
1.1	14/06/2023	Georga Edwards	QOL update. Description table added to Section 2 - Configuration
1.2	26/08/2025	Georga Edwards	Note added to section 3.3 View Employee Assigned to your Geofence

1. Overview

1.1. Purpose of the Guide

The purpose of this guide is to introduce Geofencing Clocking solution and to explain the benefits of this system.

This guide covers:

- What is Geofencing?
- Configuration of Geofences on Portal
- Warnings and Restrictions
- Employee Views
- Manager Views

1.2. What is Geofencing?

Geofencing is a virtual defined boundary which sets a perimeter, or geofence, around a specific location such as an office or store.

You define the Geofence when you specify:

- The latitude and longitude co-ordinates of the point of interest.
- The required radius in meters of the geofence.

Once the clocking app on a device has been activated and is within the Geofence it allows the user to clock in and clock out.

By using Geofencing, the system can stop employees from clocking in when they are outside the allowed radius or Geofence.



Note: The Geofence solution only applies to clocking via the Native App. It does not apply to clocking via Portal or the mobile web app.

The accuracy of the location reported depends on the following factors:

- The phone being used (i.e., GPS chip, model/operating system)

- Cellular network
- Wi-Fi network
- Battery saving mode on/off
- Weather
- Interference with the device such as trees etc.

In general, the radius of the Geofence should be wide enough to compensate for these factors.

 **Note:** It is usually recommended that the **minimum** size of the geofence is 80 metres.

2. Configuration

2.1. How to access the Mobile App Clocking – Geofence Admin Screen

You can access the Mobile App Clocking – Geofence Admin Screen via the WFM Admin Dashboard. To do this

1. Go to *WFM Admin Dashboard*.
2. Select **WFM Configuration**.
3. Select **Mobile App Clocking – Geofence Admin**.

Geofence Name	Radius (in Metres)	Restriction Level	Max Tolerance (%)	Assigned To	# of Employees	Status	Actions
Amy	1000	Warn	10	Group 7264	87	Active	⋮
Benton Street	80	Warn	10		0	Active	⋮
Gaelscoil Ui Riordain	50	Warn	0	Matt's group	152	Active	⋮
Shanballymore GAA (Warn)	100	Warn	100	72644	87	Active	⋮

The screen can be filtered to display All/Active or Inactive Geofence's created.

The **Mobile App Clocking – Geofence Admin** screen contains the following fields:

Field	Details		
Geofence Name	This displays the name of the Geofence.		
Radius (in Metres)	This displays the radius, in metres, of the Geofence. This defines the boundary which sets a perimeter around your location. Once users are within the perimeter, they can clock in and out.		
	It is usually recommended that the minimum size of the geofence radius is 80 metres.		
Restriction Level	This displays the Restriction Level applied to the Geofence. The Restriction Level Options are:		
	Option	Definition	System Action

Field	Details		
	STOP	When an employee tries to clock in outside of the Geofence. (or) Location Services are not enabled. (or) If the employee is using a mock location.	The System stops the employee clocking with a message stating they are outside of the Geofence.
	WARN	An employee tries to clock in outside of the allowed Geofence. (or) Location Service are not enabled.	The clocking is flagged as an exception. The system records the device location, the GPS point of interest location and the GPS perimeter radius.
	If Warn is selected, you will need to select a reason code. Reason Codes options may be among the following: • No Reason Codes Applicable • Other Paid Leave Reason Codes • Sick Reason Codes • Unpaid Leave Reason Codes		
	ALLOW	An employee clocks in within the Geofence.	The employee can clock in freely.
Max Tolerance (%)	 Note: You can decide at which level you wish to define the restriction of the Geofence. The restriction controls which level the geofence is applied to, such as Employee level or Geofence level. The default restriction type is at the Geofence level. For further information, See Section 2.3		
	Tolerance is the distance outside the Geofence radius which the employee is allowed to clock in. The tolerance itself is represented as a halo around the geofence. Halo clockings are flagged as <i>Tolerance Applied</i> exceptions for information purposes. For example, an employee may have		

Field	Details
	clocked within the extended part of the geofence, but their reported location is not 100% accurate. You can turn the tolerance on or off depending on the Geofence, as well as specifying the maximum tolerance as a percentage of the radius.
Assigned To	This displays the Criteria Group assigned to the Geofence.
# of Employees	This displays the number of employee's assigned to the Geofence.
Active/Inactive	This displays the status of the Geofence.

2.2. Create a Geofence

1. From the *Mobile App Clocking – Geofence Admin* screen, click **Add Geofence**.
2. **Enter** your Geofence Name.
3. Then using **Search** enter your location and move the pin to the exact location you wish to geofence. The screen allows you to select either the map or satellite image.

The screenshot displays the 'Edit Geofence' interface. On the left, there is a 'Details' section with the following fields:

- Geofence Name***: A text input field with the placeholder 'Apple'.
- Latitude of Centre Point***: A text input field containing the value '37.33223061303045'.
- Longitude of Centre Point***: A text input field containing the value '-122.03081338825102'.
- Radius***: A text input field with a dropdown menu set to '100'.

The main area features a map titled 'Select an area' with a search bar and 'MAP'/'SATELLITE' toggle buttons. A red pin is placed on the map, and a green circle indicates the geofence radius. The bottom right corner has a green 'SAVE' button.

4. Once located the Latitude and Longitude automatically update.
5. Enter the **Radius** for your Geofence. It is usually recommended that the **minimum** size of the geofence is 80 metres. This defines the boundary which sets a perimeter around your location. Once users are within the perimeter, they can clock in and out.

6. Decide on the **Tolerance percentage** by moving the toggle. Tolerance is the distance outside of the Geofence radius in which you allow the employee to clock in. Once the tolerance is added in, the tolerance area is shown around the existing Geofence.
7. Using the drop-down menu select the **Restriction level**, options are Stop, Warn, Allow (see above table for definitions).
8. Once you're happy with your selection, click **Save**.
9. Your Geofence will now display on the Mobile App Clocking – Geofence Admin screen.

2.3. Manage Overrides

You can override the restriction level assigned to a Geofence at an employee level. For example, you may have applied a restriction level of Warn to your Geofence but want to allow Managers an alternative option. To do this:


1. From the *Mobile App Clocking – Geofence Admin* screen, click **Manage Overrides**.
2. Click on **Add Override**.
3. Using the drop-down menu, select the **Employee** you wish to override the restriction level.
4. Using the drop-down menu, select the new **Restriction Level** to apply to the employee.
5. Click **OK**.
6. The employee will now show on the Manage Overrides screen, displaying their associated Job Title, Work Group, Department and New Restriction Level.

To Remove an Override:

1. From the *Mobile App Clocking – Geofence Admin* screen, click **Manage Override**.
2. Click on **Add Override**.
3. **Search** for the employee you wish to remove the Override Restriction Level for.
4. Using their 3-dot menu, click **Delete**.
5. A warning message will display, click **Yes**.
6. The employee will default back to the Geofence applied Restriction Level.

3. Manage a Geofence

The Mobile App Clocking – Geofence Admin screen is where Administrators can manage a Geofence.



Geofence Name	Radius (in Metres)	Restriction Level	Max Tolerance (%)	Assigned To	# of Employees	
Amy	1000	Warn	10	Group 7264	87	Active
Benton Street	80	Warn	10		0	Active
Gaelscoil Ui Riordain	50	Warn	0	Matt's group	152	Active
Shanballymore GAA (Warn)	100	Warn	100	72644	87	Active

Using a Geofence associated 3-dot menu you can:

- Edit
- Assign Group
- View Employees
- Deactivate

3.1. Edit your Geofence

Select the Geofence you want to update and from the 3-dot menu, select **Edit**. From here you can amend the criteria applied to your Geofence. For example, change the Radius or Restriction Level.


To capture any changes made, click **Save**.

3.2. Assign Criteria Groups to your Geofence

As part of the Geofence setup process you are required to add criteria groups to your Geofence, this is done from the Mobile App Clocking – Geofence Admin screen.

Criteria Groups are customisable user-defined groups made up of employees who hold the same specified attributes on their contracts. They allow you to group employees based on reference data in their employee record. For example, you could group all employees in a particular department or location.

Your criteria groups will need to be created before they can be assigned to your Geofence.



3.2.1. Create a Criteria Group


1. Select the Geofence you want to update and from the 3-dot menu, select **Assign to Group**.
2. Click the **Manage Criteria Groups** button, from here you can manage all existing criteria groups and create new criteria groups.
3. Click **Add** to create a new group.
4. Give your group a **Name** and select the **type**, then click **OK**.
5. Click on your required reference data from the left-hand menu.
6. Select the relevant attributes from the **Available** column and use the arrow to move them to the **Assigned** column, this list is automatically saved.
7. Using the breadcrumb to return to the **Manage Criteria Groups** screen and confirm the criteria is correct, you can delete/edit rules using the 3-dot menu.
8. Repeat to create all required criteria groups.

3.2.2. Assign your Criteria Group(s) to your Geofence

Now your criteria groups are created they are ready to be assigned to the Geofence. To do this:

1. Use the breadcrumb to return to **Manage Criteria Groups for your Geofence**.
2. Click **Assign New Group**.

3. Use the **drop-down menu** to select the criteria group you would like assign and click **OK**; this is automatically saved.
4. Repeat the process to add additional criteria groups to your Geofence, if required
5. Use the breadcrumb to return to the **Mobile App Clocking – Geofence Admin** screen and confirm the criteria is correct.
6. The Geofence will now display the group(s) assigned and number of employees.



Mobile App Clocking - Geofence Admin						ADD GEOFENCE	MANAGE OVERRIDES
WFM Admin Dashboard > Mobile App Clocking - Geofence Admin							
Search Geofences		All					
Geofence Name	Radius (in Metres)	Restriction Level	Max Tolerance (%)	Assigned To	# of Employees		
Amy	1000	Warn	10	Group 7264	87	Active	⋮
Apple	80	Allow	20	Example Group	21	Active	⋮
Benton Street	80	Warn	10		0	Active	⋮

3.2.3. Groupings

The Groupings within Geofencing refer to an existing item which is associated within the HR Structural Data.

- Employees can be linked to one or more Geofence.
- Geolocation Groupings can be linked to HR Reference Data including Location or Cost Centre using features such as criteria groups. For further information on Criteria Groups see [Section 3.2](#)

3.3. View Employee Assigned to your Geofence

Select the Geofence you want to view the list of assigned employees for and from the 3-dot menu, select **View Employees**. This will return the list of assigned employees displaying their Job Title, Work Group, Department & the Criteria Group they are Assigned By.



Note: The search function supports **employee name** only. Searching by **employee number** is not currently available.

3.4. Deactivate a Geofence

Select the Geofence you want to deactivate and from the 3-dot menu, select **Deactivate**.

Your Geofence will now display as Inactive.

4. Geofencing Checklist

Use the checklist below to make sure that you have everything you need:

- ✓ **GRANT ADMIN ACCESS:** Do you have access to the Geofence Clocking Admin screen.
See [Section 7.1](#)
- ✓ **CONFIGURE GEOFENCES:** Have you created the Geofences applicable to your organisation and assigned them to employees? See [Section 2](#) and [Section 3](#)
- ✓ **GRANT EMPLOYEE ACCESS:** Have the employees been given the applicable Native App Geofence menu security access. [See Section 7.2](#)
- ✓ **CONFIGURE TIME EXCEPTIONS:** (if Applicable) Have you turned on the Time Exceptions. [See Section 7.3](#)

5. Manager Views


In this section, we detail screens which the manager will see once they have been given access to Geofencing.

5.1. Time Exceptions

Time Exceptions can be accessed by Managers and Administrators via either the *Manager Dashboard* or *Workforce Management Dashboard*.

5.1.1. Manager Dashboard – Time Exception Widget


The Time Exception widget can be found on the Manager Dashboard under Time and shows the clockings which need action over a given period. It also allows users to **View Scheduler** by clicking on the button on the top right-hand side of the screen.



5.1.2. Workforce Management - Time Exceptions Screen

Managers can view any clocking exceptions on the *Time Exceptions Screen*. This can be found on the Workforce Management Dashboard, Time. The Geofence Tab is a visibility screen only and does not require any action.


Native App – Mobile App Geofence Clocking - User Guide



5.1.3. Time Exception View Map

Leading on from the Exception Screen, the manager can drill down into the specific exceptions to see where they occurred and plot them on the map.

This is useful for the admin or manager to see when an employee, or the team, clocked in and the exceptions they generated.



5.2. Insight and Geofencing


Insight can be used by Managers or Admins to view Geofence clocking details including any exceptions which may have arisen. Using the Insight Geo Map Component, users can plot the clocking times onto a map using the clock location longitude and latitude co-ordinates.

Insight can be used in situations such as the following:

Native App – Mobile App Geofence Clocking - User Guide

- To give managers an understanding of the volume of exceptions versus non-exceptions.
- To review all exceptions for a particular employee to understand their patterns and behaviours.
- Give managers visibility of where their team are clocking in or out.


The Insight Report shows the exceptions plotted on the map and where they occurred.



6. Employee Views

In this section we will see some of the screens and messages which the employee will encounter while using Geofence Clockings.

6.1. Clocking In/Out



6.2. Using Location

When entering the Mobile App Clocking screen, the Mobile Device's operating System will prompt the user to allow People XD to use the location.


Users can choose between **Allow Once**, **Allow While Using App** or **Don't Allow** to deny permission.

The location is needed to establish where the employee is when they are clocking so that the location can be validated against the geofence. The location of the clocking is stored in PeopleXD and the location is visible to themselves, their Manager and Admin.

6.3. Allowing Access to Device Location

When you use Geofencing for the first time, a window pops up in which the system prompts you to allow it access to your device location.

1. To allow the access, Press **Yes**.



2. The system then reconfirms your action.
3. Press **OK**.




6.4. Returning User

If you have previously denied the prompt to allow location, when you return you have the choice to **Enable Settings**.

This opens the OS settings screen, the same as the existing *Open Settings* on the main screen.

Pressing **No** dismisses the window and no actions are taken.



6.5. Dynamic Map

With Geofencing, the map is dynamic and moves as the mobile device itself moves. This means the employee can tell their position in relation to the geofence and they can tell whether they are approaching a tolerance.

The location of the mobile device is represented by a blue dot or circle. This blue dot updates as the mobile devices moves. The geofence colour reacts to the employee's movements within the Geofence. The colours of the Geofence are detailed in the table below.


Colour	Details
Red	Red shows if the employee is outside the Geofence.
Green	Green shows if the employee is in the Geofence.
Orange	Orange shows if the employee is within the tolerance halo of the Geofence.

Larger circles signify that the location is less accurate. The location is always reported as the centre point of the blue circle. However, the device can be anywhere within in the circle. The radius of the blue circle represents its accuracy level.

The *Mobile App Clock in/Clock out* screen continuously polls the location services so you may see the circle go from large to small as the accuracy of the location improves.

6.6. Geofence - Historical Clockings

Using the calendar on the mobile app, the employee can view the previous clockings which have been made.



Drilling further in this, the employee can get further details on the name of the specific Geofence, detail on the geofence exception where applicable as well as the distance from the Geofence when they clocked in.




Note: Geofence details are not available to view via the Portal *Employee Dashboard*.

6.7. Restriction Levels

There are several restriction levels which are used to control the geofence. Each one has a specific criteria as well as a system message to inform the user what action needs to be taken in each instance. For further information on the restriction levels see the table in [Section 2](#).

6.8. Employee Messages

In the table below are the default messages an employee may encounter as they clock in or out depending on your distance from the Geofence.



Note: The Employee default messages can be changed by using the Language Pack on your profile settings.

Action	Default Message
Clocking Outside Geofence	Stop – You seem to be outside of the Clocking Area.
	Stop - Clocking Areas are shown on the map. Please try again when are within the marked area.
	Warn – You seem to be outside of the Clocking Area.

Action	Default Message
	Warn – If you continue, please note your clocking will be subject to your manager’s attention. You may move into the marked area to avoid this.
Location Service Turned Off	Stop – App does not have access to your location. Stop – You are not allowed to clock in. To continue, please enable <i>Location</i> in System Settings. Warn – App does not have access to your location. Warn – You are allowed to clock in or out, but your clocking will be subject to manager attention.
Mobile App does not have Location Services	Stop – App does not have access to your location. Stop - You are allowed to clock in or out, but your clocking will be subject to manager attention. To avoid this, please enable Location in Application Settings. Warn – App does not have access to your location. Warn – You are allowed to clock in or out, but your clocking will be subject to manager attention. To avoid this, please enable Location in Application Settings.
Mock Location Reported	Stop – You seem to be using a mock location. Stop – Please disable location mocking and start again. Warn – You seem to be using a mock location. Warn - If you continue, please note your clocking will be subject to manager attention. You may disable location mocking to disable this.

 **Note:** If you choose to use free text as part of your Geoclocking solutions, any comment entered is stored against the clocking and if applicable the clocking location and be visible to authorised users. Therefore, any confidential information should not be divulged.

7. Menu Options

To use the Geofencing feature on the native app, the menu option needs to be enabled for employees on Portal.

7.1. Administrators Access

Administrators need these to set up a Geofence around the specific office or building.

In order to be able to set up and maintain geofences, users will need to be given access to the Geofence Admin screen. You can either assign the Geofence Admin profile to specific admin users or update an existing admin profile.

7.1.1. Assign Geofence Clocking Admin Profile to Specific Admin Users

1. Navigate to *Security*.
2. Select **User Management**.
3. Within **System Users** search for the relevant user.
4. Using the associated 3-dot menu click **Manage Account**.
5. Using the Menu Profiles tab search for **GEOFENCE_CLOCKING_ADMIN_USER**.
6. **Enable** the Active toggle.
7. Repeat for all Admin users requiring access.

7.1.2. Update an Existing Admin Menu Profile

1. Navigate to *Security*.
2. Select **User Management**.
3. Select **Menu Profiles**.
4. Retrieve the applicable Admin menu profile and choose **Manage Menu Options**.
5. Search for each security menu item. Enable by flagging to **Active**.

The following menu options are needed for **Administrators** to configure Geofencing:

Menu Option	Menu ID	System
CorePortal - Workforce Management Admin	MAIN_MENU.WRKMGMTADMIN	CoreProtal
WFM Configuration	MAIN_MENU.WFM_CONFIG	CorePortal
Admin Geofencing	CONFIG_SET_MENU.ADMIN_GEOFENCING	CorePortal
Clockings	MAIN_MENU.WS_CLOCKINGS	Web Service
Create Geofencing	WS_CLOCKINGS_MENU.POST_GEOFENCING	Web Service
Create Geofencing groups assigned	WS_CLOCKINGS_MENU.POST_GEOFENCING_GROUPS_ASSIGNED	Web Service
Create Geofencing Overrides	WS_CLOCKINGS_MENU.POST_GEOFENCING_OVERRIDES	Web Service
Delete Geofencing	WS_CLOCKINGS_MENU.DELETE_GEOFENCING_ID	Web Service
Delete Geofencing Groups Assigned	WS_CLOCKINGS_MENU.DELETE_GEOFENCING_GROUPS_ASSIGNED	Web Service
Delete Geofencing Overrides	WS_CLOCKINGS_MENU.DELETE_GEOFENCING_OVERRIDES_ID	Web Service
Get Geofencing	WS_CLOCKINGS_MENU.GET_GEOFENCING	Web Service
Get Geofencing Exception	WS_CLOCKINGS_MENU.GET_GEOFENCING_EXCEPTION	Web Service
Get Geofencing Groups Assigned	WS_CLOCKINGS_MENU.GET_GEOFENCING_GROUPS_ASSIGNED_ID	Web Service
Get Geofencing Overrides	WS_CLOCKINGS_MENU.GET_GEOFENCING_OVERRIDES	Web Service
Update Geofencing	WS_CLOCKINGS_MENU.PATCH_GEOFENCING_ID	Web Service
Org	MAIN_MENU.WS_ORG	Web Service
Create Group Criteria	WS_ORG_MENU.POST_GROUP_CRITERIA	Web Service
Create Group Criteria Details	WS_ORG_MENU.POST_GROUP_CRITERIA_DETAILS	Web Service

Menu Option	Menu ID	System
Get group orggroupitems	WS_ORG_MENU.GET_GROUP_ORGGROUPITEMS_ID	Web Service
Get group orggroups	WS_ORG_MENU.GET_GROUP_ORGGROUPS	Web Service
People	MAIN_MENU.WS_PEOPLE	Web Service
Get criteriagroups profile	WS_PEOPLE_MENU.GET_CRITERIAGROUPS_PROFILE_ID	Web Service
Get criteriagroups profile total	WS_PEOPLE_MENU.GET_CRITERIAGROUPS_PROFILE_TOTAL_ID	Web Service
Get roster	WS_PEOPLE_MENU.GET_ROSTER	Web Service
Refdata	MAIN_MENU.WS_REFDATA	Web Service
Get bytype	WS_REFDATA_MENU.GET_BYTYPE_TYPE	Web Service

7.2. Employee Access

The following menu options and web services are needed to grant **User** access to Geofence Clockings.

Menu Option	Menu ID	System
Get config featureflags	WS_NATIVE_MENU.GET_CONFIG_FEATUREFLAGS	Web Service
Get appointments	WS_PROFILE_MENU.GET_APPOINTMENTS	Web Service
Get geofencing	WS_CLOCKINGS_MENU.GET_GEOFENCING	Web Service
Get reasoncodes groups	WS_ROSTER_MENU.GET_REASONCODES_GROUPS	Web Service

7.3. Time Exceptions Access

The following menu options and webservices are needed to configure the *Time Exceptions Screen*.

Menu Option	System	
CorePortal - Time Exceptions - Geofence	MAIN_MENU.EXCEPTION_GEOFENCE_ACCESS	CorePortal
Get geofencing exception	WS_CLOCKINGS_MENU.GET_GEOFENCING_EXCEPTION	Web Service