



Allocate Elastic IP-Address to the EC2 Instance:

Step 1: Click on **All services**.


Step 2: Click on the [EC2](#).




Step 3: Click on the Launch Instances.



Step 4: Give the EC2 instance **name** or **tag** -> "EC2-IP-Address" is name in my case.




Step 5: Choose **Amazon Machine Image** for your instance.




Step 6: Choose an Instance type.

Step 7: Choose the Key Pair or Create the Key pair.



Step 8: Click on the **Create Security Group**, then Click on the EDIT button.



▼ Network settings [Info](#) Edit

Network [Info](#)
vpc-066d8b2c4a30ca9f3

Subnet [Info](#)
No preference (Default subnet in any availability zone)

Auto-assign public IP [Info](#)
Enable

Firewall (security groups) [Info](#)
A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.


☒ Create security group ☐ Select existing security group

We'll create a new security group called 'launch-wizard-5' with the following rules:


- ☒ Allow SSH traffic from Anywhere
0.0.0.0/0
Helps you connect to your instance
- ☒ Allow HTTPS traffic from the internet
To set up an endpoint, for example when creating a web server
- ☒ Allow HTTP traffic from the internet

[back](#) Looking for language selection? Find it in the new [Unified Settings](#)  © 2022, Amazon Inter


Step 9: Must be Disable the Auto Assign public IP.



Step 11: Scroll down and Click on the **Elastic IPs**.




Step 12: Click on the **Allocate Elastic IP Address**.



Elastic IP Address setting - Default setting.




Step 13: Click on the **Allocate**.



Step 14: Click on the **IP Address**, you will see the **Allocated IP Address 52.66.151.107**.

Step 15: Select the IP-Address -> Click on the **Action**, then select the **Associate Elastic IP Address**.



Associate Elastic IP Address -> Instance - **Choose an instance** and Select the instance where you want to allocate IP Address.

Step 16: Click on the **Associate Button**

Elastic IP address: 52.66.151.107

Resource type
Choose the type of resource with which to associate the Elastic IP address.

☒ Instance
☐ Network interface

Warning: If you associate an Elastic IP address to an instance that already has an Elastic IP address associated, this previously associated Elastic IP address will be disassociated but still allocated to your account. [Learn more](#)

Instance
i-0c9aaced2c37f6e97

Private IP address
The private IP address with which to associate the Elastic IP address.
Choose a private IP address

Reassociation
Specify whether the Elastic IP address can be reassociated with a different resource if it already associated with a resource.
☐ Allow this Elastic IP address to be reassociated

Buttons: Cancel, Associate



Step 17: Go to the Instance and Select the **Instance** and now you can see the **Public IPv4 Address 52.66.151.107**.

Instances (1/2) Info

Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone
EC2-IP-Address	i-0c9aaced2c37f6e97	Running	t2.micro	2/2 checks passed	No alarms	ap-south-1b
ec2-ip	i-0f27bfc3c0b2075df	Terminated	t2.micro	-	No alarms	ap-south-1b

Instance: i-0c9aaced2c37f6e97 (EC2-IP-Address)

Details | Security | Networking | Storage | Status checks | Monitoring | Tags

Instance summary Info

Instance ID: i-0c9aaced2c37f6e97 (EC2-IP-Address)

IPv6 address: -

Hostname type: -

Public IPv4 address: 52.66.151.107 | [open address](#)

Instance state: Running

Private IP DNS name (IPv4 only): -

Private IPv4 addresses: 172.31.11.200

Public IPv4 DNS: ec2-52-66-151-107.ap-south-1.compute.amazonaws.com | [open address](#)

Activate Windows. Go to Settings to activate Windows.

