


Topology =



Router password security / Type 5 Encryption =

249836K Bytes of NVRAM System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#username amit secret cisco@123
Router(config)#line console 0
Router(config-line)#login local
Router(config-line)#exit
Router(config)#
Router(config)#line aux 0
Router(config-line)#login local
Router(config-line)#exit
Router(config)#
Router(config)#enable secret cisco123
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#
```

Then log out and reconnect. The router should ask =

```
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit

Router con0 is now available

Press RETURN to get started.

User Access Verification

Username: amit
Password:

Router>
```

IP address configuration to Router =

```
--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface fastethernet 0/0
R1(config-if)#ip address 10.0.0.10 255.0.0.0
R1(config-if)#no shutdown



R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

R1(config-if)#do show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.0.0.10       YES manual up          down
FastEthernet0/1 unassigned      YES unset  administratively down down
Vlan1          unassigned      YES unset  administratively down down
R1(config-if)#interface fastethernet 0/1
R1(config-if)#ip address 180.180.0.1 255.255.0.0
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

R1(config-if)#do show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 10.0.0.10       YES manual up          down
FastEthernet0/1 180.180.0.1     YES manual up          down
Vlan1          unassigned      YES unset  administratively down down
R1(config-if)#
```

Copy data RAM to NVRAM and BACKUP to TFTP server =



```

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>
Router>en
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface fastethernet 0/0
R1(config-if)#ip address 10.0.0.10 255.0.0.0
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

R1(config-if)#do show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0  10.0.0.10       YES manual up          down
FastEthernet0/1  unassigned      YES unset  administratively down down
Vlan1           unassigned      YES unset  administratively down down

R1(config-if)#interface fastethernet 0/1
R1(config-if)#ip address 180.180.0.1 255.255.0.0
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

R1(config-if)#do show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0  10.0.0.10       YES manual up          down
FastEthernet0/1  180.180.0.1     YES manual up          down
Vlan1           unassigned      YES unset  administratively down down
R1(config-if)#

```

[illegible]

Recovery Backup to Server=

```

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface fastethernet 0/0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#do copy tftp startup-config
Address or name of remote host []? 10.0.0.100
Source filename []? Router-config
Destination filename [startup-config]?

Accessing tftp://10.0.0.100/Router-config...
Loading Router-config from 10.0.0.100: !
[OK - 608 bytes]

608 bytes copied in 3.013 secs (201 bytes/sec)
Router(config-if)#do show startup-config
Using 608 bytes
!
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname Router
!

```

```
ip cef  
no ipv6 cef  
!  
!  
!  
!  
license udi pid CISCO2811/K9 sn FTX1017HF70-  
!  
!  
!  
!  
!  
!  
!  
! spanning-tree mode pvst  
!  
!  
!  
!  
!  
interface FastEthernet0/0  
 ip address 10.0.0.1 255.0.0.0  
 duplex auto  
 speed auto  
!  
interface FastEthernet0/1  
 no ip address  
 duplex auto  
 speed auto  
 shutdown  
!  
interface Vlan1  
 no ip address  
 shutdown
```

```
!  
!  
interface FastEthernet0/0  
ip address 10.0.0.1 255.0.0.0  
duplex auto  
speed auto  
!  
interface FastEthernet0/1  
no ip address  
duplex auto  
speed auto  
shutdown  
!  
interface Vlan1  
no ip address  
shutdown  
!  
ip classless  
!  
ip flow-export version 9  
!  
!  
!  
!  
!  
!  
!  
line con 0  
!  
line aux 0  
!  
line vty 0 4  
login  
!  
!  
!  
end  
  
Router(config-if) #
```