vengine

0.1.0

Generated by Doxygen 1.9.1

Chapter 1

Class Index

1.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Chapter 2

Class Documentation

2.1 ven::Buffer Class Reference

Public Member Functions

- **Buffer** (Device &device, VkDeviceSize instanceSize, uint32_t instanceCount, VkBufferUsageFlags usage↩ Flags, VkMemoryPropertyFlags memoryPropertyFlags, VkDeviceSize minOffsetAlignment=1)
- **Buffer** (const Buffer &)=delete
- Buffer & **operator=** (const Buffer &)=delete
- VkResult map (VkDeviceSize size=VK_WHOLE_SIZE, VkDeviceSize offset=0)
- void unmap ()
- void writeToBuffer (const void ∗data, VkDeviceSize size=VK_WHOLE_SIZE, VkDeviceSize offset=0) const
- VkResult flush (VkDeviceSize size=VK_WHOLE_SIZE, VkDeviceSize offset=0) const
- VkDescriptorBufferInfo descriptorInfo (const VkDeviceSize size=VK_WHOLE_SIZE, const VkDeviceSize offset=0) const
- VkResult invalidate (VkDeviceSize size=VK_WHOLE_SIZE, VkDeviceSize offset=0) const
- void writeToIndex (const void ∗data, const VkDeviceSize index) const
- VkResult flushIndex (const VkDeviceSize index) const
- VkDescriptorBufferInfo descriptorInfoForIndex (const VkDeviceSize index) const
- VkResult invalidateIndex (const VkDeviceSize index) const
- VkBuffer **getBuffer** () const
- void ∗ **getMappedMemory** () const
- uint32_t **getInstanceCount** () const
- VkDeviceSize **getInstanceSize** () const
- VkDeviceSize **getAlignmentSize** () const
- VkBufferUsageFlags **getUsageFlags** () const
- VkMemoryPropertyFlags **getMemoryPropertyFlags** () const
- VkDeviceSize **getBufferSize** () const

2.1.1 Member Function Documentation

2.1.1.1 descriptorInfo()

```
VkDescriptorBufferInfo ven::Buffer::descriptorInfo (
            const VkDeviceSize size = VK_WHOLE_SIZE,
            const VkDeviceSize offset = 0 ) const  [inline]
```

Create a m_buffer info descriptor

Parameters

size	(Optional) Size of the m_memory range of the descriptor
offset	(Optional) Byte offset from beginning

Returns

VkDescriptorBufferInfo of specified offset and range

2.1.1.2 descriptorInfoForIndex()

```
VkDescriptorBufferInfo ven::Buffer::descriptorInfoForIndex (
            const VkDeviceSize index ) const  [inline]
```

Create a m_buffer info descriptor

Parameters

index	Specifies the region given by index ∗ m_alignmentSize

Returns

VkDescriptorBufferInfo for instance at index

2.1.1.3 flush()

```
VkResult ven::Buffer::flush (
            VkDeviceSize size = VK_WHOLE_SIZE,
            VkDeviceSize offset = 0 ) const
```

Flush a m_memory range of the m_buffer to make it visible to the device

Note

Only required for non-coherent m_memory

Parameters

size	(Optional) Size of the m_memory range to flush. Pass VK_WHOLE_SIZE to flush the complete m_buffer range.
offset	(Optional) Byte offset from beginning

Returns

VkResult of the flush call

2.1.1.4 flushIndex()

```
VkResult ven::Buffer::flushIndex (
            const VkDeviceSize index ) const  [inline]
```

Flush the m_memory range at index ∗ m_alignmentSize of the m_buffer to make it visible to the device

Parameters

index	Used in offset calculation

2.1.1.5 invalidate()

```
VkResult ven::Buffer::invalidate (
            VkDeviceSize size = VK_WHOLE_SIZE,
            VkDeviceSize offset = 0 ) const
```

Invalidate a m_memory range of the m_buffer to make it visible to the host

Note

Only required for non-coherent m_memory

Parameters

size	(Optional) Size of the m_memory range to invalidate. Pass VK_WHOLE_SIZE to invalidate the complete m_buffer range.
offset	(Optional) Byte offset from beginning

Returns

VkResult of the invalidate call

2.1.1.6 invalidateIndex()

```
VkResult ven::Buffer::invalidateIndex (
            const VkDeviceSize index ) const  [inline]
```

Invalidate a m_memory range of the m_buffer to make it visible to the host

Note

Only required for non-coherent m_memory

Parameters

index	Specifies the region to invalidate: index ∗ m_alignmentSize

Returns

VkResult of the invalidate call

2.1.1.7 map()

```
VkResult ven::Buffer::map (
            VkDeviceSize size = VK_WHOLE_SIZE,
            VkDeviceSize offset = 0 )
```

Map a m_memory range of this m_buffer. If successful, m_mapped points to the specified m_buffer range.

Parameters

size	(Optional) Size of the m_memory range to map. Pass VK_WHOLE_SIZE to map the complete m_buffer range.
offset	(Optional) Byte offset from beginning

Returns

VkResult of the m_buffer mapping call

2.1.1.8 unmap()

```
void ven::Buffer::unmap ( )
```

Unmap a m_mapped m_memory range

Note

Does not return a result as vkUnmapMemory can't fail

2.1.1.9 writeToBuffer()

```
void ven::Buffer::writeToBuffer (
            const void * data,
            VkDeviceSize size = VK_WHOLE_SIZE,
            VkDeviceSize offset = 0 ) const
```

Copies the specified data to the m_mapped m_buffer. Default value writes whole m_buffer range

Parameters

data	Pointer to the data to copy
size	(Optional) Size of the data to copy. Pass VK_WHOLE_SIZE to flush the complete m_buffer range.
offset	(Optional) Byte offset from beginning of m_mapped region

2.1.1.10 writeToIndex()

```
void ven::Buffer::writeToIndex (
            const void * data,
            const VkDeviceSize index ) const  [inline]
```

Copies "m_instanceSize" bytes of data to the m_mapped m_buffer at an offset of index * m_alignmentSize

Parameters

data	Pointer to the data to copy
index	Used in offset calculation

The documentation for this class was generated from the following file:

- include/VEngine/Buffer.hpp

2.2 ven::DescriptorPool::Builder Class Reference

Public Member Functions

- **Builder** (Device &device)
- Builder & **addPoolSize** (VkDescriptorType descriptorType, uint32_t count)
- Builder & **setPoolFlags** (VkDescriptorPoolCreateFlags flags)
- Builder & **setMaxSets** (uint32_t count)
- std::unique_ptr< DescriptorPool > **build** () const

The documentation for this class was generated from the following file:

- include/VEngine/Descriptors.hpp

2.3 ven::DescriptorSetLayout::Builder Class Reference

Public Member Functions

- **Builder** (Device &device)
- Builder & **addBinding** (uint32_t binding, VkDescriptorType descriptorType, VkShaderStageFlags stage↩ Flags, uint32_t count=1)
- std::unique_ptr< DescriptorSetLayout > **build** () const

The documentation for this class was generated from the following file:

- include/VEngine/Descriptors.hpp

2.4 ven::Model::Builder Struct Reference

Public Member Functions

- void **loadModel** (const std::string &filename)

Public Attributes

- std::vector< Vertex > **vertices**
- std::vector< uint32_t > **indices**

The documentation for this struct was generated from the following file:

- include/VEngine/Model.hpp

2.5 ven::Camera Class Reference

Public Member Functions

- void **setOrthographicProjection** (float left, float right, float top, float bottom, float near, float far)
- void **setPerspectiveProjection** (float fovy, float aspect, float near, float far)
- void **setViewDirection** (glm::vec3 position, glm::vec3 direction, glm::vec3 up=glm::vec3{0.F, -1.F, 0.F})
- void **setViewTarget** (glm::vec3 position, glm::vec3 target, glm::vec3 up=glm::vec3{0.F, -1.F, 0.F})
- void **setViewYXZ** (glm::vec3 position, glm::vec3 rotation)
- const glm::mat4 & **getProjection** () const
- const glm::mat4 & **getView** () const
- const glm::mat4 & **getInverseView** () const

The documentation for this class was generated from the following file:

- include/VEngine/Camera.hpp

2.6 myLib::Clock Class Reference

Public Member Functions

- void **restart** ()
- void **pause** ()
- void **resume** ()
- Time **getElapsedTime** () const

The documentation for this class was generated from the following file:

- lib/local/static/myLib/include/myLib/Clock/Clock.hpp

2.7 ven::DescriptorPool Class Reference

Classes

- class Builder

Public Member Functions

- **DescriptorPool** (Device &device, uint32_t maxSets, VkDescriptorPoolCreateFlags poolFlags, const std::vector< VkDescriptorPoolSize > &poolSizes)
- **DescriptorPool** (const DescriptorPool &)=delete
- DescriptorPool & **operator=** (const DescriptorPool &)=delete
- bool **allocateDescriptor** (VkDescriptorSetLayout descriptorSetLayout, VkDescriptorSet &descriptor) const
- void **freeDescriptors** (const std::vector< VkDescriptorSet > &descriptors) const
- void **resetPool** () const

Friends

- class **DescriptorWriter**

The documentation for this class was generated from the following file:

- include/VEngine/Descriptors.hpp

2.8 ven::DescriptorSetLayout Class Reference

Classes

- class Builder

Public Member Functions

- **DescriptorSetLayout** (Device &device, const std::unordered_map< uint32_t, VkDescriptorSetLayoutBinding > &bindings)
- **DescriptorSetLayout** (const DescriptorSetLayout &)=delete
- DescriptorSetLayout & **operator=** (const DescriptorSetLayout &)=delete
- VkDescriptorSetLayout **getDescriptorSetLayout** () const

Friends

- class **DescriptorWriter**

The documentation for this class was generated from the following file:

- include/VEngine/Descriptors.hpp

2.9 ven::DescriptorWriter Class Reference

Public Member Functions

- **DescriptorWriter** (DescriptorSetLayout &setLayout, DescriptorPool &pool)
- DescriptorWriter & **writeBuffer** (uint32_t binding, const VkDescriptorBufferInfo *bufferInfo)
- DescriptorWriter & **writeImage** (uint32_t binding, const VkDescriptorImageInfo *imageInfo)
- bool **build** (VkDescriptorSet &set)
- void **overwrite** (const VkDescriptorSet &set)

The documentation for this class was generated from the following file:

- include/VEngine/Descriptors.hpp

2.10 ven::Device Class Reference

Public Member Functions

- **Device** (Window &window)
- **Device** (const Device &)=delete
- Device & **operator=** (const Device &)=delete
- **Device** (Device &&)=delete
- Device & **operator=** (Device &&)=delete
- VkCommandPool **getCommandPool** () const
- VkDevice **device** () const
- VkSurfaceKHR **surface** () const
- VkQueue **graphicsQueue** () const
- VkQueue **presentQueue** () const
- SwapChainSupportDetails **getSwapChainSupport** () const
- uint32_t **findMemoryType** (uint32_t typeFilter, VkMemoryPropertyFlags propertiesp) const
- QueueFamilyIndices **findPhysicalQueueFamilies** () const
- VkFormat **findSupportedFormat** (const std::vector< VkFormat > &candidates, VkImageTiling tiling, VkFormatFeatureFlags features) const
- void **createBuffer** (VkDeviceSize size, VkBufferUsageFlags usage, VkMemoryPropertyFlags propertiesp, VkBuffer &buffer, VkDeviceMemory &bufferMemory) const
- VkCommandBuffer **beginSingleTimeCommands** () const
- void **endSingleTimeCommands** (VkCommandBuffer commandBuffer) const
- void **copyBuffer** (VkBuffer srcBuffer, VkBuffer dstBuffer, VkDeviceSize size) const
- void **copyBufferToImage** (VkBuffer buffer, VkImage image, uint32_t width, uint32_t height, uint32_t layerCount) const
- void **createImageWithInfo** (const VkImageCreateInfo &imageInfo, VkMemoryPropertyFlags properties, VkImage &image, VkDeviceMemory &imageMemory) const
- VkPhysicalDevice **getPhysicalDevice** () const
- VkQueue **getGraphicsQueue** () const

Public Attributes

- const bool **enableValidationLayers** = true
- VkPhysicalDeviceProperties **m_properties**

The documentation for this class was generated from the following file:

- include/VEngine/Device.hpp

2.11 ven::Engine Class Reference

Public Member Functions

- **Engine** (uint32_t=DEFAULT_WIDTH, uint32_t=DEFAULT_HEIGHT, const std::string &title=DEFAULT_↩ TITLE.data())
- **Engine** (const Engine &)=delete
- Engine **operator=** (const Engine &)=delete
- Window & **getWindow** ()
- void **mainLoop** ()

The documentation for this class was generated from the following file:

- include/VEngine/Engine.hpp

2.12 ven::FrameCounter Class Reference

Public Member Functions

- void **update** (const float deltaTime)
- float **getFps** () const
- float **getFrameTime** () const

The documentation for this class was generated from the following file:

- include/VEngine/FrameCouter.hpp

2.13 ven::FrameInfo Struct Reference

Public Attributes

- int **frameIndex**
- float **frameTime**
- VkCommandBuffer **commandBuffer**
- Camera & **camera**
- VkDescriptorSet **globalDescriptorSet**
- Object::Map & **objects**

The documentation for this struct was generated from the following file:

- include/VEngine/FrameInfo.hpp

2.14 ven::GlobalUbo Struct Reference

Public Attributes

- glm::mat4 **projection** {1.F}
- glm::mat4 **view** {1.F}
- glm::mat4 **inverseView** {1.F}
- glm::vec4 **ambientLightColor** {1.F, 1.F, 1.F, .02F}
- std::array< PointLight, MAX_LIGHTS > **pointLights**
- int **numLights**

The documentation for this struct was generated from the following file:

- include/VEngine/FrameInfo.hpp

2.15 ven::KeyboardController Class Reference

Classes

- struct KeyMappings

Public Member Functions

- void **moveInPlaneXZ** (GLFWwindow *window, float dt, Object &object) const

Public Attributes

- KeyMappings **m_keys** {}
- float **m_moveSpeed** {3.F}
- float **m_lookSpeed** {1.5F}

The documentation for this class was generated from the following file:

- include/VEngine/KeyboardController.hpp

2.16 ven::KeyboardController::KeyMappings Struct Reference

Public Attributes

- int **moveLeft** = GLFW_KEY_A
- int **moveRight** = GLFW_KEY_D
- int **moveForward** = GLFW_KEY_W
- int **moveBackward** = GLFW_KEY_S
- int **moveUp** = GLFW_KEY_SPACE
- int **moveDown** = GLFW_KEY_LEFT_SHIFT
- int **lookLeft** = GLFW_KEY_LEFT
- int **lookRight** = GLFW_KEY_RIGHT
- int **lookUp** = GLFW_KEY_UP
- int **lookDown** = GLFW_KEY_DOWN

The documentation for this struct was generated from the following file:

- include/VEngine/KeyboardController.hpp

2.17 ven::Model Class Reference

Classes

- struct Builder
- struct Vertex

Public Member Functions

- **Model** (Device &device, const Builder &builder)
- **Model** (const Model &)=delete
- void **operator=** (const Model &)=delete
- void **bind** (VkCommandBuffer commandBuffer) const
- void **draw** (VkCommandBuffer commandBuffer) const

Static Public Member Functions

- static std::unique_ptr< Model > **createModelFromFile** (Device &device, const std::string &filename)

The documentation for this class was generated from the following file:

- include/VEngine/Model.hpp

2.18 ven::Object Class Reference

Public Types

- using **Map** = std::unordered_map< id_t, Object >

Public Member Functions

- **Object** (const Object &)=delete
- Object & **operator=** (const Object &)=delete
- **Object** (Object &&)=default
- Object & **operator=** (Object &&)=default
- id_t **getId** () const

Static Public Member Functions

- static Object **createObject** ()
- static Object **makePointLight** (float intensity=10.F, float radius=0.1F, glm::vec3 color=glm::vec3(1.F))

Public Attributes

- std::shared_ptr< Model > **model** {}
- glm::vec3 **color** {}
- Transform3DComponent **transform3D** {}
- std::unique_ptr< PointLightComponent > **pointLight** = nullptr

The documentation for this class was generated from the following file:

- include/VEngine/Object.hpp

2.19 ven::PipelineConfigInfo Struct Reference

Public Member Functions

- **PipelineConfigInfo** (const PipelineConfigInfo &)=delete
- PipelineConfigInfo & **operator=** (const PipelineConfigInfo &)=delete

Public Attributes

- std::vector< VkVertexInputBindingDescription > **bindingDescriptions**
- std::vector< VkVertexInputAttributeDescription > **attributeDescriptions**
- VkPipelineInputAssemblyStateCreateInfo **inputAssemblyInfo** {}
- VkPipelineRasterizationStateCreateInfo **rasterizationInfo** {}
- VkPipelineMultisampleStateCreateInfo **multisampleInfo** {}
- VkPipelineColorBlendAttachmentState **colorBlendAttachment** {}
- VkPipelineColorBlendStateCreateInfo **colorBlendInfo** {}
- VkPipelineDepthStencilStateCreateInfo **depthStencilInfo** {}
- std::vector< VkDynamicState > **dynamicStateEnables**
- VkPipelineDynamicStateCreateInfo **dynamicStateInfo** {}
- VkPipelineLayout **pipelineLayout** = nullptr
- VkRenderPass **renderPass** = nullptr
- uint32_t **subpass** = 0

The documentation for this struct was generated from the following file:

- include/VEngine/Shaders.hpp

2.20 ven::PointLight Struct Reference

Public Attributes

- glm::vec4 **position** {}
- glm::vec4 **color** {}

The documentation for this struct was generated from the following file:

- include/VEngine/FrameInfo.hpp

2.21 ven::PointLightComponent Struct Reference

Public Attributes

- float **lightIntensity** = 1.0F

The documentation for this struct was generated from the following file:

- include/VEngine/Object.hpp

2.22 ven::PointLightSystem Class Reference

Public Member Functions

- **PointLightSystem** (Device &device, VkRenderPass renderPass, VkDescriptorSetLayout globalSetLayout)
- **PointLightSystem** (const PointLightSystem &)=delete
- PointLightSystem & **operator=** (const PointLightSystem &)=delete
- void **render** (const FrameInfo &frameInfo) const

Static Public Member Functions

- static void **update** (const FrameInfo &frameInfo, GlobalUbo &ubo)

The documentation for this class was generated from the following file:

- include/VEngine/System/PointLightSystem.hpp

2.23 ven::QueueFamilyIndices Struct Reference

Public Member Functions

- bool **isComplete** () const

Public Attributes

- uint32_t **graphicsFamily** {}
- uint32_t **presentFamily** {}
- bool **graphicsFamilyHasValue** = false
- bool **presentFamilyHasValue** = false

The documentation for this struct was generated from the following file:

- include/VEngine/Device.hpp

2.24 myLib::Random Class Reference

Static Public Member Functions

- static int **randomInt** (int min, int max)
- static int **randomInt** ()
- static float **randomFloat** (float min, float max)
- static float **randomFloat** ()

The documentation for this class was generated from the following file:

- lib/local/static/myLib/include/myLib/Random.hpp

2.25 ven::Renderer Class Reference

Public Member Functions

- **Renderer** (Window &window, Device &device)
- **Renderer** (const Renderer &)=delete
- Renderer & **operator=** (const Renderer &)=delete
- VkRenderPass **getSwapChainRenderPass** () const
- float **getAspectRatio** () const
- bool **isFrameInProgress** () const
- VkCommandBuffer **getCurrentCommandBuffer** () const
- int **getFrameIndex** () const
- VkCommandBuffer **beginFrame** ()
- void **endFrame** ()
- void **beginSwapChainRenderPass** (VkCommandBuffer commandBuffer) const

Static Public Member Functions

- static void **endSwapChainRenderPass** (VkCommandBuffer commandBuffer)

The documentation for this class was generated from the following file:

- include/VEngine/Renderer.hpp

2.26 ven::RenderSystem Class Reference

Public Member Functions

- **RenderSystem** (Device &device, VkRenderPass renderPass, VkDescriptorSetLayout globalSetLayout)
- **RenderSystem** (const RenderSystem &)=delete
- RenderSystem & **operator=** (const RenderSystem &)=delete
- void **renderObjects** (const FrameInfo &frameInfo) const

The documentation for this class was generated from the following file:

- include/VEngine/System/RenderSystem.hpp

2.27 ven::Shaders Class Reference

Public Member Functions

- **Shaders** (Device &device, const std::string &vertFilepath, const std::string &fragFilepath, const PipelineConfigInfo &configInfo)
- **Shaders** (const Shaders &)=delete
- Shaders & **operator=** (const Shaders &)=delete
- void **bind** (const VkCommandBuffer commandBuffer) const

Static Public Member Functions

- static void **defaultPipelineConfigInfo** (PipelineConfigInfo &configInfo)

The documentation for this class was generated from the following file:

- include/VEngine/Shaders.hpp

2.28 ven::SimplePushConstantData Struct Reference

Public Attributes

- glm::mat4 **modelMatrix** {1.F}
- glm::mat4 **normalMatrix** {1.F}

The documentation for this struct was generated from the following file:

- include/VEngine/System/RenderSystem.hpp

2.29 ven::SwapChain Class Reference

Public Member Functions

- **SwapChain** (Device &deviceRef, const VkExtent2D windowExtentRef)
- **SwapChain** (Device &deviceRef, const VkExtent2D windowExtentRef, std::shared_ptr< SwapChain > previous)
- **SwapChain** (const SwapChain &)=delete
- SwapChain & **operator=** (const SwapChain &)=delete
- VkFramebuffer **getFrameBuffer** (const unsigned long index) const
- VkRenderPass **getRenderPass** () const
- VkImageView **getImageView** (const int index) const
- size_t **imageCount** () const
- VkFormat **getSwapChainImageFormat** () const
- VkExtent2D **getSwapChainExtent** () const
- uint32_t **width** () const
- uint32_t **height** () const
- float **extentAspectRatio** () const
- VkFormat **findDepthFormat** () const
- VkResult **acquireNextImage** (uint32_t *imageIndex) const
- VkResult **submitCommandBuffers** (const VkCommandBuffer *buffers, const uint32_t *imageIndex)
- bool **compareSwapFormats** (const SwapChain &swapChainp) const

Static Public Attributes

- static constexpr int **MAX_FRAMES_IN_FLIGHT** = 2

The documentation for this class was generated from the following file:

- include/VEngine/SwapChain.hpp

2.30 ven::SwapChainSupportDetails Struct Reference

Public Attributes

- VkSurfaceCapabilitiesKHR **capabilities**
- std::vector< VkSurfaceFormatKHR > **formats**
- std::vector< VkPresentModeKHR > **presentModes**

The documentation for this struct was generated from the following file:

- include/VEngine/Device.hpp

2.31 myLib::Time Class Reference

Public Member Functions

- **Time** (const double seconds)
- int **asSeconds** () const
- int **asMilliseconds** () const
- int **asMicroseconds** () const

The documentation for this class was generated from the following file:

- lib/local/static/myLib/include/myLib/Clock/Time.hpp

2.32 ven::Transform3DComponent Struct Reference

Public Member Functions

- glm::mat4 **mat4** () const
- glm::mat3 **normalMatrix** () const

Public Attributes

- glm::vec3 **translation** {}
- glm::vec3 **scale** {1.F, 1.F, 1.F}
- glm::vec3 **rotation** {}

The documentation for this struct was generated from the following file:

- include/VEngine/Object.hpp

2.33 ven::Model::Vertex Struct Reference

Public Member Functions

- bool **operator==** (const Vertex &other) const

Static Public Member Functions

- static std::vector< VkVertexInputBindingDescription > **getBindingDescriptions** ()
- static std::vector< VkVertexInputAttributeDescription > **getAttributeDescriptions** ()

Public Attributes

- glm::vec3 **position** {}
- glm::vec3 **color** {}
- glm::vec3 **normal** {}
- glm::vec2 **uv** {}

The documentation for this struct was generated from the following file:

- include/VEngine/Model.hpp

2.34 ven::Window Class Reference

Public Member Functions

- **Window** (const uint32_t width, const uint32_t height, const std::string &title)
- GLFWwindow * **createWindow** (uint32_t width, uint32_t height, const std::string &title)
- void **createWindowSurface** (VkInstance instance, VkSurfaceKHR *surface) const
- GLFWwindow * **getGLFWindow** () const
- VkExtent2D **getExtent** () const
- bool **wasWindowResized** () const
- void **resetWindowResizedFlag** ()

The documentation for this class was generated from the following file:

- include/VEngine/Window.hpp

Index