




Install Cisco AnyConnect VPN




Instructions


1. When your account has been created you will get an email that looks like this.
Click **SelfService** link



2. Click **Log in**



3. Submit *SelfService id* and *Password* from the email to log in
4. Click **Start the enrollment process**



5. Click **Continue**

CGI Access Manager [Log Out]
Self Service

Home Enrollment Self Service Download page Information About

Välkommen till CGIs aktiveringsprocess

För att kunna använda ditt konto måste du följa den här guiden.

Stegen i denna process varierar beroende på hur ditt konto är konfigurerat, eller på vilka alternativ du väljer.

Continue

© CGI Sverige AB

6. Select *Microsoft Authenticator (for mobile)* and click **Continue**

CGI Access Manager [Log Out]
Self Service

Home Enrollment Self Service Download page Information About

Select Password generator type

☐ Google Authenticator (for mobile)
☒ Microsoft Authenticator (for mobile)
☐ AccMan Authenticator (for Windows PC)
☐ Hardware

Du skall nu välja vilken typ av lösenordsgenerator du föredrar.
Beroende på inställningarna för ditt konto är kanske alla alternativ inte tillgängliga.

Förutom hårdvarudosa, kan du välja mellan tre olika typer, en som installeras i din PC, en som installeras i din mobiltelefon eller en för surfplatta (iPad/Android).

OBS!

Om du väljer en PC-baserad lösenordsgenerator, då **måste** du spara installationsfilen lokalt på din dator innan du påbörjar installationen.
Om du är osäker på om du använder 32-bit Windows eller 64-bit versionen, välj 32-bitars.

För att kunna använda lösenordsgenerator i mobiltelefonen så måste mobiltelefonen vara installerad så att den kan använda internet. För Android, iPhone och Windows Phone mobiler måste du ha användarkonto i Android Market, iTunes Store respektive Windows Store.
Samma krav gäller för surfplatta.

Continue

© CGI Sverige AB

7. Click **Continue**

CGI



Access Manager [\[Log Out \]](#)
Self Service

HomeEnrollmentSelf ServiceDownload pageInformationAbout

Microsoft Authenticator Enrollment - Introduction

1. Välj en personlig PIN kod

2. Nedladdning av programvaran
App Store för Apple eller Google Play för Android.

3. Generera ett Microsoft Authenticator konto
Verifiering av kontot.

Continue

© CGI Sverige AB

8. Submit your personal  *PIN-code* and click **Continue**

CGI



Access Manager [\[Log Out \]](#)
Self Service

HomeEnrollmentSelf ServiceDownload pageInformationAbout

Microsoft Authenticator Enrollment - 1. Personal PIN code

Account ID: [redacted]@jula.se
Name: [redacted]
Profile: [redacted]
Select Personal PIN code:

PIN code

Please remember your PIN code.


The PIN code should be used by you, when you logon in combination with a logon password (a One Time Password).

If you forget your PIN code, you can request for a new.

Continue

© CGI Sverige AB

9. Follow the instructions and click **Continue**



10. Scan the QR-code using your Authenticator application. Then enter the verification code from your Authentication application in the box and click **Verify** and then **Continue**

CGI

Access Manager

Self Service

[\[Log Out \]](#)

Home

Enrollment

Self Service

Download page

Information

About

Microsoft Authenticator Enrollment - 3. Add a password generator

If you already have a Microsoft Authenticator token for this account, please remove it before you add this new one.

1. Open the Microsoft Authenticator app.
2. Add a new account by scanning the barcode shown at the right. Choose the type "Other"
3. After the Microsoft Authenticator account is created, generate a verification code / password and enter it in the box below.

Verification code / Password:

Verify

Label:


Jula External




Continue

© CGI Sverige AB

11. Search for *Cisco Secure Client* and open it



12. To connect using AnyConnect VPN, enter *myvpn.cgi.se* and click **Connect**




13. Submit the following:

- a. Username is the *Account ID* from the email
- b. Password is the Authenticator application code + your  PIN-code
(that you submitted in step 8)
In this example, the current Authenticator code is *123456*



If your  PIN-code is 8989 then the Password will be: 1234568989

Finally, click **OK** to connect



If the connection is successful, the window will disappear and you are done!