

more

Control paged output in Command Window

Syntax

```
more on
more off
more(n)
A = more( __ )
```

Description

`more on` enables paging of the output in the MATLAB® Command Window. When paging is enabled, MATLAB displays output one page at a time.

[example](#)

- To advance to the next page of output, press the **Space** key.
- To advance to the next line of output, press the **Return** key.
- To stop displaying the current output, press the **Q** key. Do not use **Ctrl+C** to exit `more`, otherwise MATLAB can return an error.

`more off` disables paging of the output in the Command Window. By default, paging is disabled.

[example](#)

`more(n)` enables paging and sets the page length to `n` lines.

[example](#)

By default, the length of a page is equal to the number of lines available for display in the MATLAB Command Window. If you set the page length to a specific value, MATLAB uses that value for the page size, regardless of the size of the command window.

To restore the default page length, run the command `more off` followed by the command `more on`.

`A = more( __ )` returns the current page size in number of lines. You can use this syntax with any of the input argument combinations in the previous syntaxes.

[example](#)

Examples

[collapse all](#)

View Help One Page at a Time

Use the `more` function to control the number of help lines displayed in the command window.

Enable paging in the Command Window and then get help on the `plot` function.

```
more on
help plot
```

`plot` Linear plot.

`plot(X,Y)` plots vector `Y` versus vector `X`. If `X` or `Y` is a matrix, then the vector is plotted versus the rows or columns of the matrix, whichever line up. If `X` is a scalar and `Y` is a vector, disconnected line objects are created and plotted as discrete points vertically at `X`.

`plot(Y)` plots the columns of `Y` versus their index.

If `Y` is complex, `plot(Y)` is equivalent to `plot(real(Y),imag(Y))`.

--more--

Press the **Space** key to view the help page by page until the last page is displayed. Call `more off` to disable paging.

Change Command Window Page Size

Set the page size in the Command Window and then restore the original page size.

Enable paging and set the page size to 5, storing the previous size in the variable `previousSize`.

```
previousSize = more(5)
```

```
previousSize =
```

```
9
```

Display the help text for the `plot` function.

```
more on
help plot
```

```
plot Linear plot.
```

```
plot(X,Y) plots vector Y versus vector X. If X or Y is a matrix,
then the vector is plotted versus the rows or columns of the matrix,
whichever line up. If X is a scalar and Y is a vector, disconnected
line objects are created and plotted as discrete points vertically at
```

```
--more--
```

Use the **Space** key to view the help page by page until the last page is displayed.

Restore the page size and display the help for the `plot` function again.

```
more(previousSize)
help plot
```

```
plot Linear plot.
```

```
plot(X,Y) plots vector Y versus vector X. If X or Y is a matrix,
then the vector is plotted versus the rows or columns of the matrix,
whichever line up. If X is a scalar and Y is a vector, disconnected
line objects are created and plotted as discrete points vertically at
X.
```

```
plot(Y) plots the columns of Y versus their index.
```

```
If Y is complex, plot(Y) is equivalent to plot(real(Y),imag(Y)).
```

```
--more--
```

Use the **Space** key to view the help page by page until the last page is displayed. Call `more off` to disable paging.

Input Arguments

n — Page size
positive integer

Page size, specified as a positive integer.

Tips

- To see the status of `more`, type `get(0, 'More')`. MATLAB returns either `on` or `off`, indicating whether paging of the output is enabled or disabled.

Version History

Introduced before R2006a

See Also

[diary](#)

Topics

[Format Output](#)

YOU MIGHT ALSO BE INTERESTED IN

