| ~~           | ш |  |
|--------------|---|--|
|              |   |  |
| $\mathbf{v}$ |   |  |
|              | , |  |

|        | IOGIN<br>Requirement   | Test No. | Test name              | Purpose   | Input  | Input file             |
|--------|--|----------|------------------------|---|--|------------------------|
|        |  | R1T1     | idle logout            | Cannot logout before logging in   | logout   | None                   |
|        |  | R1T2     | idle createacct        | Cannot create account before logging in   | createacct   | None                   |
|        | No transaction before login  | R1T3     | idle deleteacct        | Cannot delete<br>account before<br>logging in   | deleteacct   | None                   |
|        | belore logili  | R1T4     | idle deposit           | Cannot deposit before logging in  | deposit  | None                   |
|        |  | R1T5     | idle withdraw          | Cannot withdraw before logging in   | withdraw   | None                   |
|        |  | R1T6     | idle transfer          | Cannot transfer before logging in   | transfer   | None                   |
|        | no subsequent<br>login should be<br>accepted after a<br>login, until after<br>a logout | R2T1     | subsequent login       | No subsequent login   | login-login  | None                   |
| Only t | Ü  | R3T1     | illegal mode<br>input  | mode name<br>other than<br>"agent" and<br>"machine" are<br>illegal  | login-anyinput<br>other than<br>"machine" and<br>"agent" | None                   |
|        | Only two modes<br>are available  | R3T2     | machine mode           | after login as<br>machine mode,<br>read valid<br>accounts list file<br>and accept only<br>ATM transaction | login-machine  | valid accounts<br>list |
|        |  | R3T3     | agent mode             | after login as<br>agent mode,<br>read valid<br>accounts list file<br>and accept any<br>other transaction  | login-agent  | valid accounts<br>list |
| C      | Machine mode only accepts  | R4T1     | machine-<br>createacct | Cannot create<br>account under<br>ATM mode  | login-machine-<br>createacct                             | None                   |
|        | ATM transaction<br>and logout  | R4T2     | machine-<br>deleteacct | Cannot delete<br>account under<br>ATM mode  | login-machine-<br>deleteacct                             | None                   |
|        |  |          |                        |   |  |                        |

| Agent mode<br>accepts all R5T1<br>transaction | agent-<br>transaction | agent mode<br>aceepts all<br>transaction | agent-any<br>transaction | None |
|---|-----------------------|--|--------------------------|------|
|---|-----------------------|--|--------------------------|------|

| Output<br>error prompt for<br>user to log in | Output file None |
|--|------------------|
| error prompt for user to log in              | None             |
| error prompt for user to log in              | None             |
| error prompt for user to log in              | None             |
| error prompt for user to log in              | None             |
| error prompt for user to log in              | None             |
| error subsequent<br>login                    | None             |
| error illegal<br>mode                        | None             |
| None   | None             |
| None   | None             |
| error prompt for agent mode                  | None             |
| error prompt for agent mode                  | None             |

None

None