

TMS, DMS and CMS Usage Guide for Falcon BMS 4.38.1

Carlos “Metal” Nader

Version VERSION+DATE | Progress: Chapters X/7 | Tables Chapter X | January 2026

Contents

List of HOTAS Tables	ii
0.0.1 SOI-Capable Displays and Context Dependency	1

List of HOTAS Tables

0.0.1 SOI-Capable Displays and Context Dependency

Not all displays can be designated as SOI, and the availability of SOI designation varies by master mode and MFD format.

The master mode determines which displays are eligible for SOI designation. In some operational contexts, the HUD can be designated as SOI, allowing the pilot to manage HUD symbology through HOTAS inputs. In other contexts, particularly air-to-air engagements, SOI designation is restricted to MFD formats only. This restriction ensures that primary sensor displays remain the focus of HOTAS control during time-critical tactical situations.

Similarly, not all MFD formats are SOI-capable. Sensor formats that accept targeting and cursor control inputs—such as radar, targeting pod, and weapon displays—can be designated as SOI. Informational or configuration formats that do not require direct sensor interaction cannot be designated as SOI. This design aligns SOI availability with operational function: only displays that benefit from HOTAS cursor and targeting control are SOI-capable.

The Targeting Pod (TGP) is a representative example of an SOI-capable sensor format. In Falcon BMS, TGP functionality is provided by external pods such as the AN/AAQ-33 Sniper XR ATP or AN/AAQ-14 LANTIRN, which must be loaded on the aircraft before flight. When equipped and powered, the TGP MFD format accepts cursor slew, TMS designation commands, and sensor cueing inputs across multiple master modes (NAV, A-A, A-G). If no TGP is present or the pod is off, the TGP format cannot be displayed or designated as SOI. Detailed TGP operational procedures and TMS command structures are covered in Section ?? (TGP air-to-air tracking) and Section 4.4 (TGP air-to-ground employment); comprehensive pod system details are documented in Dash-34 § 2.6.

Understanding these context dependencies is essential for effective HOTAS use. The pilot must recognize not only how to designate a display as SOI, but also whether such designation is permitted in the current operational context. For complete operational reference tables showing SOI availability by master mode and the full list of valid and invalid MFD formats, see Section ??.