

Support
Help
Forum
Contact Us
Follow us

Blog

Translate

iPhone / iPad VLC Streamer VLC Remote Watchover Off GTD 2 Min Timer iPhone / iPad Chill Remote File Getter Video Analysis Go Away! Mac Os Multi Monitor Wallpaper AV Rules Right Click Booster Icns Builder Android Image Viewer Android
VLC Streamer
VLC Remote
Windows
Bonjour Browser

Translate

Custom Search


Set up VLC for the VLC Remote - Linux

back to setup main page


NB: These setup instructions are for VLC 2.1 or later. If you are using an earlier version of VLC, then please click here.

A) Enable the HTTP Interface


- 1. Open the VLC settings
 - VLC Menu/Tools/Preferences
- 2. Enable 'All Settings' (by default VLC only shows the most used settings)
 - · Click on the 'All' button at the bottom left of the screen



- 3. Enable the interface
 - Click on Interface, then Main interfaces
 - Select the 'Web' checkbox.
 - This should show 'http' in the text box



B) Set your password



- 1. Click on the Lua icon on the left
 - Enter a password under Lua HTTP
- 2. The default password we use is 'vlcremote' if you use this password, then the remote will connect automatically without you needing to re-enter your password.
- 3. Click save to save your preferences
- 4. Quit VLC and reopen it.

C) Note for Web OS or Windows Phone users

Your phones don't have the ability to scan Bonjour like the iPhone does, so you won't automatically see remotes, and you won't see any cones next to available remotes.

Instead, you'll have to click on 'Manual Pairing' in the first page of the app and enter the IP address of your machine. (Type ifconfig for IP address details at the terminal).

D) That's it!

By now, you should be able to see your computer in the VLC Remotes page under 'Found Computers'. If VLC is running on your computer, then you should see a Traffic cone next to the computer entry.

You can then select that computer and control it remotely.

Troubleshooting...

If you can't connect, try the troubleshooting page.

© Hobbyist Software - All rights reserved. Hobbyist Software is a trading name of Hobbyist Software Limited. Registered office 12 Fraley Rd, Westbury on Trym, Bristol. Registered in England. Company no:7876492