

Temporary Card Enrollment Tool



Summary

The Temporary Card Enrollment tool allows for proximity cards to be enrolled as temporary cards with an expiration time. This allows administrators to distribute temporary cards to users that will be valid for a determined period of time. For example, if a contract employee needs to authenticate at a device for a day only, a proximity card can be enrolled as a temporary card, and then the employee can use that card for that day. After the expiration time is exceeded, the card is no longer valid and the employee will no longer be able to authenticate with the card.


Temporary Card Enrollment

The tool can be installed on any desktop and connects to the HPAC server that contains AD Authenticator and then connects to the IRM database. A CZ208 card reader or X3D03A card reader must be connected to the desktop. Follow the steps below to enroll a temporary card.

IMPORTANT: The TempCardEnrollment.exe, CardReader.dll and CardReader32.dll must be copied to a workstation where a card reader is connected, and all three files must be in the same folder. The DeleteTempCard.exe must be copied to the HPAC server.

IMPORTANT: On the HPAC server, make sure the IRM data storage is set to Database. And in HPAC > Settings > Database > IRM Database Configuration, make sure the Server Name field contains the SQL server name and instance.


1. Run the TempCardEnrollment.exe file on a workstation that has a card reader connected.
2. Type the HPAC server name or IP address in “HPAC server name” field then press the ENTER key to connect to the HPAC server where AD-Authenticator is used.



3. When “Card masking” is enabled, the masking configuration is read directly from the HP AC server.

IMPORTANT: For card masking to work, the DataDecodeDefaults.xml file must be copied from the “HP Access Control\Shared\4.3.3\Configuration\ProximityCards” folder to the “HP Access Control\AD-Authenticator” folder.

4. In the “Validity Period” field, set the expiration time for the temporary card.
5. Click the “Enroll card” button, then present the card at the connected card reader. A message displays when the card is successfully enrolled as a temporary card.



6. The card is enrolled as a temporary card in the database and can now be enrolled to a user. When the validity period expires, the card can no longer be used for authentication. To use the same card again, remove the card from the temporary cards list or re-enroll the card as a temporary card with a new expiration time.

NOTE: To view all temporary cards that have been enrolled and the expiration times, click the “List cards” button.

NOTE: To check if a specific card is enrolled as a temporary card and to view the card’s expiration time, click the “Check card” button, then present the card at the connected card reader.

NOTE: To remove a card from the list of temporary cards, click the “Remove card” button, then present the card at the connected card reader.

NOTE: All parameters will be saved and kept for the next time the tool is re-used.

Also included is a command line tool to delete the card from the database when the expiration time has exceeded, so that the user will no longer be able to authenticate with the card. The command line tool, DeleteTempCard.exe, needs to be executed on the HPAC server where AD-Authenticator is installed. This is recommended to be scheduled in the Windows task scheduler to periodically delete expired temporary cards.

NOTE: If Windows authentication is used in HPAC to connect to the IRM database, the scheduler must use an account with admin rights to run the EXE file.