

Lab Task



THE UNIVERSITY OF LAHORE

Department of CS&IT

=====

LAB_TASK (week-7)

=====

Name: Ayan Ahmad

SAP ID: 70147501

Class / Section: BSCS-6C


Submitted To: Sir Muhammad Shahzad

Subject: Computer Networks



Lab Task

Topology Pic:



1. VTP-Server :


```
VTP-Server
Physical Config CLI Attributes

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

VTP-SERVER>enable
VTP-SERVER#
VTP-SERVER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
VTP-SERVER(config)#
VTP-SERVER(config)#
VTP-SERVER(config)#interface FastEthernet0/1
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/2
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/3
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/2
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/1
VTP-SERVER(config-if)#vtp mode server
Device mode already VTP SERVER.
VTP-SERVER(config)#vtp domain UOL
Changing VTP domain name from uol to UOL
VTP-SERVER(config)#%SW_VLAN-6-VTP_DOMAIN_NAME_CHG: VTP domain name changed to UOL.
```

2. VTP-Transparent :


Lab Task



The screenshot shows a terminal window titled "VTP-Transparent" with tabs for Physical, Config, CLI, and Attributes. The CLI tab is active, displaying a series of commands and their outputs. The commands entered are: "en", "conf t", "vtp mode transparent", "vtp domain uol", and "vtp max-configs 100". The outputs show that the device is already in VTP transparent mode and the domain name is already set to uol.

```
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#en
VTP-TRANSPARENT#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VTP-TRANSPARENT(config)#vtp mode transparent
Device mode already VTP TRANSPARENT.
VTP-TRANSPARENT(config)#vtp domain uol
Domain name already set to uol.
VTP-TRANSPARENT(config)#
VTP-TRANSPARENT(config)#vtp max-configs 100
```

3. VTP-client-cs (sw1) :




The screenshot shows a terminal window titled "sw1" with tabs for Physical, Config, CLI, and Attributes. The CLI tab is active, displaying a series of commands and their outputs. The commands entered are: "en", "show vtp status", "conf t", and a series of "vtp" commands. The outputs show the current VTP status, including version, revision, maximum VLANs supported, and operating mode.

```
sw1
Physical Config CLI Attributes
VTP-CLIENT-CS>en
VTP-CLIENT-CS#show vtp status
VTP Version : 1
Configuration Revision : 0
Maximum VLANs supported locally : 255
Number of existing VLANs : 5
VTP Operating Mode : Client
VTP Domain Name : uol
VTP Pruning Mode : Disabled
VTP V2 Mode : Disabled
VTP Traps Generation : Disabled
MD5 digest : 0xEC 0xA1 0x08 0xF4 0xCC 0x42 0x01 0x16
Configuration last modified by 0.0.0.0 at 0-0-00 00:00:00
VTP-CLIENT-CS#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
```


CS:

- PC-PT — 10.0.0.1

Lab Task




- **PC-PT — 10.0.0.2**



4. VTP-client-se (sw2) :

Lab Task



```
sw2
Physical Config CLI Attributes
port type.

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to
down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to
up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to
down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to
up

VTP-CLIENT-SE>en
VTP-CLIENT-SE#show vtp status
VTP Version          : 1
Configuration Revision : 0
Maximum VLANs supported locally : 255
Number of existing VLANs : 5
VTP Operating Mode    : Client
VTP Domain Name       : uol
VTP Pruning Mode      : Disabled
VTP V2 Mode           : Disabled
VTP Traps Generation  : Disabled
MD5 digest            : 0xEC 0xA1 0x08 0xF4 0xCc 0x42 0x01 0x16
Configuration last modified by 0.0.0.0 at 0-0-00 00:00:00
VTP-CLIENT-SE#
```


SE:

- PC-PT — 11.0.0.1




- PC-PT — 11.0.0.2

Lab Task




5. VTP-client-math(sw3):



Math


- PC-PT — 13.0.0.1

Lab Task



The screenshot shows the 'IP Configuration' window for PC 13.0.0.1. The 'Interface' is 'FastEthernet0'. Under 'IP Configuration', 'DHCP' is selected, and 'Static' is also selected. The 'IPv4 Address' is '13.0.0.1', 'Subnet Mask' is '255.0.0.0', 'Default Gateway' is '0.0.0.0', and 'DNS Server' is '0.0.0.0'. Under 'IPv6 Configuration', 'Automatic' is selected, and 'Static' is also selected. The 'IPv6 Address' is empty, 'Link Local Address' is 'FE80::290:CFF:FED4:D9B2', 'Default Gateway' is empty, and 'DNS Server' is empty. Under '802.1X', 'Use 802.1X Security' is checked, 'Authentication' is 'MD5', 'Username' is empty, and 'Password' is empty.

- **PC-PT — 13.0.0.2**



The screenshot shows the 'IP Configuration' window for PC 13.0.0.2. The 'Interface' is 'FastEthernet0'. Under 'IP Configuration', 'DHCP' is selected, and 'Static' is also selected. The 'IPv4 Address' is '13.0.0.2', 'Subnet Mask' is '255.0.0.0', 'Default Gateway' is '0.0.0.0', and 'DNS Server' is '0.0.0.0'. Under 'IPv6 Configuration', 'Automatic' is selected, and 'Static' is also selected. The 'IPv6 Address' is empty, 'Link Local Address' is 'FE80::209:7CFF:FE54:B03D', 'Default Gateway' is empty, and 'DNS Server' is empty. Under '802.1X', 'Use 802.1X Security' is checked, 'Authentication' is 'MD5', 'Username' is empty, and 'Password' is empty. A 'Top' button is visible at the bottom left.